

# Compaq TCP/IP Services for OpenVMS

---

## Management Command Reference

Order Number: AA-PQQGH-TE

**January 2001**

This manual describes the commands used for configuring and managing the Compaq TCP/IP Services for OpenVMS product.

**Revision Information:**

This guide supersedes the *Compaq TCP/IP Services for OpenVMS Management Command Reference*, Version 5.0

**Software Version:**

Compaq TCP/IP Services for OpenVMS  
Version 5.1

**Operating Systems:**

OpenVMS Alpha Versions 7.1 and 7.2-1  
OpenVMS VAX Versions 7.1 and 7.2

**Compaq Computer Corporation  
Houston, Texas**

---

© 2001 Compaq Computer Corporation

COMPAQ, VAX, VMS, and the Compaq logo Registered in U.S. Patent and Trademark Office.

OpenVMS, PATHWORKS, and Tru64 are trademarks of Compaq Information Technologies Group, L.P. in the United States and other countries.

All other product names mentioned herein may be trademarks of their respective companies.

Confidential computer software. Valid license from Compaq required for possession, use, or copying. Consistent with FAR 12.211 and 12.212, Commercial Computer Software, Computer Software Documentation, and Technical Data for Commercial Items are licensed to the U.S. Government under vendor's standard commercial license.

Compaq shall not be liable for technical or editorial errors or omissions contained herein. The information in this document is provided "as is" without warranty of any kind and is subject to change without notice. The warranties for Compaq products are set forth in the express limited warranty statements accompanying such products. Nothing herein should be construed as constituting an additional warranty.

ZK6527

The document is available on CD-ROM.

This document was prepared using DECdocument, Version 3.3-1b.

---

# Contents

<b>Preface</b> .....	vii
<b>1 Using TCP/IP Services Management Commands</b>	
1.1 Entering Commands .....	1-1
1.1.1 Setting Configuration Parameters .....	1-4
1.1.2 Modifying the Configuration Database .....	1-4
1.1.3 Creating and Deleting Files .....	1-5
1.1.4 Adding and Deleting Records .....	1-5
1.1.5 Starting and Stopping Software .....	1-6
1.1.6 Validating Data Integrity .....	1-6
1.1.7 Managing NFS .....	1-7
1.1.8 Using NFS .....	1-7
1.1.9 Displaying Information .....	1-8
1.2 UNIX Management Commands .....	1-8
<b>2 Command Descriptions</b>	
ADD EXPORT .....	2-2
ADD PROXY .....	2-5
ANALYZE CONTAINER .....	2-8
ANALYZE MAIL .....	2-10
ANALYZE SERVICE .....	2-13
CONVERT/CONFIGURATION_BIND .....	2-15
CONVERT/UNIX BIND .....	2-16
CONVERT/UNIX HOST .....	2-18
CONVERT/UNIX NETWORK .....	2-19
CONVERT/VMS BOOTP .....	2-20
CONVERT/VMS HOST .....	2-21
CONVERT/VMS NETWORK .....	2-22
CONVERT/VMS PROXY .....	2-23
CREATE BOOTP .....	2-24
CREATE CONFIGURATION .....	2-25
CREATE CONTAINER .....	2-26
CREATE DIRECTORY .....	2-29
CREATE EXPORT .....	2-32
CREATE HOST .....	2-33
CREATE NETWORK .....	2-34
CREATE PROXY .....	2-35
CREATE ROUTE .....	2-36
DEFINE COMMUNICATION_CONTROLLER .....	2-37

DELETE COMMUNICATION_CONTROLLER .....	2-39
DELETE CONTAINER .....	2-40
DIRECTORY .....	2-41
DISABLE SERVICE .....	2-43
DISCONNECT DEVICE_SOCKET .....	2-45
DISMOUNT .....	2-46
ENABLE SERVICE .....	2-49
EXIT .....	2-51
EXPORT .....	2-52
HELP .....	2-53
IMPORT .....	2-54
LIST COMMUNICATION_CONTROLLER .....	2-57
LOOP .....	2-59
MAP .....	2-61
MOUNT .....	2-63
PING .....	2-73
REMOVE DIRECTORY .....	2-75
REMOVE EXPORT .....	2-76
REMOVE FILE .....	2-78
REMOVE MAIL .....	2-79
REMOVE PROXY .....	2-81
SEND MAIL .....	2-83
SET ARP .....	2-84
SET BOOTP .....	2-86
SET COMMUNICATION .....	2-88
SET CONFIGURATION BIND .....	2-91
SET CONFIGURATION COMMUNICATION .....	2-94
SET CONFIGURATION ENABLE SERVICE .....	2-97
SET CONFIGURATION INTERFACE .....	2-98
SET CONFIGURATION MAP .....	2-103
SET CONFIGURATION NAME_SERVICE .....	2-105
SET CONFIGURATION NOMAP .....	2-107
SET CONFIGURATION PROTOCOL .....	2-108
SET CONFIGURATION SMTP .....	2-111
SET CONFIGURATION SNMP .....	2-115
SET CONFIGURATION START ROUTING .....	2-119
SET GATED .....	2-120
SET HOST .....	2-121
SET INTERFACE .....	2-123
SET MX_RECORD .....	2-128
SET NAME_SERVICE .....	2-130
SET NETWORK .....	2-133
SET NFS_SERVER .....	2-135
SET PROTOCOL .....	2-137
SET ROUTE .....	2-140
SET SERVICE .....	2-143
SHOW ARP .....	2-150

SHOW BOOTP .....	2-151
SHOW CFS .....	2-153
SHOW COMMUNICATION .....	2-156
SHOW CONFIGURATION .....	2-158
SHOW CONFIGURATION PROTOCOL .....	2-161
SHOW DEVICE_SOCKET .....	2-162
SHOW EXPORT .....	2-165
SHOW HOST .....	2-167
SHOW INTERFACE .....	2-170
SHOW MAIL .....	2-172
SHOW MAP .....	2-174
SHOW MOUNT .....	2-175
SHOW MX_RECORD .....	2-177
SHOW NAME_SERVICE .....	2-179
SHOW NETWORK .....	2-181
SHOW NFS_SERVER .....	2-182
SHOW PORTMAPPER .....	2-183
SHOW PROTOCOL .....	2-184
SHOW PROXY .....	2-186
SHOW ROUTE .....	2-188
SHOW SERVICE .....	2-190
SHOW VERSION .....	2-194
START MAIL .....	2-195
START ROUTING .....	2-196
STOP ROUTING .....	2-198
UNMAP .....	2-199
ZERO NFS_SERVER .....	2-200

## Index

## Tables

1	TCP/IP Services Documentation .....	viii
1-1	Management Command Guidelines .....	1-2
1-2	SET Commands .....	1-4
1-3	UNIX Management Commands .....	1-8



---

# Preface

The Compaq TCP/IP Services for OpenVMS product is Compaq's implementation of the TCP/IP networking protocol suite and internet services for OpenVMS Alpha and OpenVMS VAX systems.

A layered software product, TCP/IP Services provides a comprehensive suite of functions and applications that support industry-standard protocols for heterogeneous network communications and resource sharing.

This manual describes the TCP/IP Services management commands. Use it in conjunction with the *Compaq TCP/IP Services for OpenVMS Management* manual, which describes the management tasks.

## Intended Audience

This manual is for experienced OpenVMS and UNIX system managers and assumes a working knowledge of TCP/IP networking, TCP/IP terminology, and some familiarity with the TCP/IP Services product.

If you are not familiar with the TCP/IP Services product, please review the *DIGITAL TCP/IP Services for OpenVMS Concepts and Planning* manual before using this manual to configure and manage TCP/IP components.

## Document Structure

This manual contains the following chapters:

- Chapter 1 introduces the management control program.
- Chapter 2 provides command descriptions for each management command.

## Related Documents

Table 1 lists the documents available with this version of TCP/IP Services.

**Table 1 TCP/IP Services Documentation**

Manual	Contents
<i>DIGITAL TCP/IP Services for OpenVMS Concepts and Planning</i>	<p>This manual provides conceptual information about networking and the TCP/IP protocol including a description of the Compaq implementation of the Berkeley Internet Name Domain (BIND) service and the Network File System (NFS). It outlines general planning issues to consider before configuring your system to use the TCP/IP Services software.</p> <p>This manual also describes the manuals in the documentation set, provides a glossary of terms and acronyms for the TCP/IP Services software product, and documents how to contact the InterNIC Registration Service to register domains and access Requests for Comments (RFCs).</p>
<i>Compaq TCP/IP Services for OpenVMS Release Notes</i>	<p>This text file describes new features and changes to the software including installation, upgrade, configuration, and compatibility information. These notes also describe new and existing software problems and restrictions, and software and documentation corrections.</p> <p>Print this text file at the beginning of the installation procedure and read it before you install TCP/IP Services.</p>
<i>Compaq TCP/IP Services for OpenVMS Installation and Configuration</i>	<p>This manual explains how to install and configure the TCP/IP Services product.</p>
<i>DIGITAL TCP/IP Services for OpenVMS User's Guide</i>	<p>This manual describes how to use the applications available with TCP/IP Services such as remote file operations, email, TELNET, TN3270, and network printing. This manual explains how to use these services to communicate with systems on private internets or on the worldwide Internet.</p>
<i>Compaq TCP/IP Services for OpenVMS Management</i>	<p>This manual describes how to configure and manage the TCP/IP Services product.</p> <p>Use this manual with the <i>Compaq TCP/IP Services for OpenVMS Management Command Reference</i> manual.</p>
<i>Compaq TCP/IP Services for OpenVMS Management Command Reference</i>	<p>This manual describes the TCP/IP Services management commands.</p> <p>Use this manual with the <i>Compaq TCP/IP Services for OpenVMS Management</i> manual.</p>
<i>Compaq TCP/IP Services for OpenVMS Management Command Quick Reference Card</i>	<p>This reference card lists the TCP/IP management commands by component and describes the purpose of each command.</p>
<i>Compaq TCP/IP Services for OpenVMS UNIX Command Reference Card</i>	<p>This reference card contains information about commonly performed network management tasks and their corresponding TCP/IP management and Compaq <i>Tru64</i> UNIX command formats.</p>
<i>DIGITAL TCP/IP Services for OpenVMS ONC RPC Programming</i>	<p>This manual presents an overview of high-level programming using open network computing remote procedure calls (ONC RPCs). This manual also describes the RPC programming interface and how to use the RPCGEN protocol compiler to create applications.</p>
<i>Compaq TCP/IP Services for OpenVMS Sockets API and System Services Programming</i>	<p>This manual describes how to use the Sockets API and OpenVMS system services to develop network applications.</p>

(continued on next page)



**Table 1 (Cont.) TCP/IP Services Documentation**

Manual	Contents
<i>Compaq TCP/IP Services for OpenVMS SNMP Programming and Reference</i>	This manual describes the Simple Network Management Protocol (SNMP) and the SNMP application programming interface (eSNMP). It describes the subagents provided with TCP/IP Services, utilities provided for managing subagents, and how to build your own subagents.
<i>Compaq TCP/IP Services for OpenVMS Tuning and Troubleshooting</i>	This manual provides information about how to isolate the causes of network problems and how to tune the TCP/IP Services software for the best performance.
<i>Compaq TCP/IP Services for OpenVMS Guide to IPv6</i>	This manual describes the IPv6 environment, the roles of systems in this environment, the types and function of the different IPv6 addresses, and how to configure TCP/IP Services to access the 6bone network.

For additional information about Compaq *OpenVMS* products and services, access the Compaq website at the following location:

<http://www.openvms.compaq.com/>

For a comprehensive overview of the TCP/IP protocol suite, you might find the book *Internetworking with TCP/IP: Principles, Protocols, and Architecture*, by Douglas Comer, useful.

## Reader's Comments

Compaq welcomes your comments on this manual. Please send comments to either of the following addresses:

Internet	<b>openvmsdoc@compaq.com</b>
Mail	Compaq Computer Corporation OSSG Documentation Group, ZKO3-4/U08 110 Spit Brook Rd. Nashua, NH 03062-2698

## How to Order Additional Documentation

Visit the following World Wide Web address for information about how to order additional documentation:

<http://www.openvms.compaq.com/>

If you need help deciding which documentation best meets your needs, call 800-282-6672.

## Conventions

The name TCP/IP Services means both:

- Compaq TCP/IP Services for OpenVMS Alpha
- Compaq TCP/IP Services for OpenVMS VAX

The name UNIX refers to the Compaq *Tru64* UNIX operating system.

The following conventions are used in this manual. In addition, please note that all IP addresses are fictitious.

Ctrl/ <i>x</i>	A sequence such as Ctrl/ <i>x</i> indicates that you must hold down the key labeled Ctrl while you press another key or a pointing device button.
PF1 <i>x</i>	A sequence such as PF1 <i>x</i> indicates that you must first press and release the key labeled PF1 and then press and release another key or a pointing device button.
<span style="border: 1px solid black; padding: 2px;">Return</span>	In examples, a key name enclosed in a box indicates that you press a key on the keyboard. (In text, a key name is not enclosed in a box.)  In the HTML version of this document, this convention appears as brackets, rather than a box.
...	A horizontal ellipsis in examples indicates one of the following possibilities: <ul style="list-style-type: none"><li>• Additional optional arguments in a statement have been omitted.</li><li>• The preceding item or items can be repeated one or more times.</li><li>• Additional parameters, values, or other information can be entered.</li></ul>
.	A vertical ellipsis indicates the omission of items from a code example or command format; the items are omitted because they are not important to the topic being discussed.
( )	In command format descriptions, parentheses indicate that you must enclose choices in parentheses if you specify more than one.
[ ]	In command format descriptions, brackets indicate optional choices. You can choose one or more items or no items. Do not type the brackets on the command line. However, you must include the brackets in the syntax for OpenVMS directory specifications and for a substring specification in an assignment statement.
	In command format descriptions, vertical bars separate choices within brackets or braces. Within brackets, the choices are optional; within braces, at least one choice is required. Do not type the vertical bars on the command line.
{ }	In command format descriptions, braces indicate required choices; you must choose at least one of the items listed. Do not type the braces on the command line.
<b>bold text</b>	This typeface represents the introduction of a new term. It also represents the name of an argument, an attribute, or a reason.
<i>italic text</i>	Italic text indicates important information, complete titles of manuals, or variables. Variables include information that varies in system output (Internal error <i>number</i> ), in command lines ( <i>/PRÓDUCER=name</i> ), and in command parameters in text (where <i>dd</i> represents the predefined code for the device type).
UPPERCASE TEXT	Uppercase text indicates a command, the name of a routine, the name of a file, or the abbreviation for a system privilege.

Monospace text

Monospace type indicates code examples and interactive screen displays.

This typeface indicates UNIX system output or user input, commands, options, files, directories, utilities, hosts, and users.

In the C programming language, this typeface identifies the following elements: keywords, the names of independently compiled external functions and files, syntax summaries, and references to variables or identifiers introduced in an example.

-

A hyphen at the end of a command format description, command line, or code line indicates that the command or statement continues on the following line.

numbers

All numbers in text are assumed to be decimal unless otherwise noted. Nondecimal radices—binary, octal, or hexadecimal—are explicitly indicated.



---

# Using TCP/IP Services Management Commands

The TCP/IP Services product provides a management command interface you use to configure and manage the software. These commands let you perform the following tasks:

- Configure and reconfigure components
- Modify parameters of components
- Configure customer-developed services
- Enable and disable running components
- Monitor the running software

## 1.1 Entering Commands

To start the management control program, type TCPIP at the DCL prompt. For example:

```
$ TCPIP
TCPIP>
```

At the TCPIP> prompt, you can enter commands described in this manual or display online help. Type EXIT to exit the management control program, or press Ctrl/C to abort a command.

Help is also available at the DCL prompt by typing HELP TCPIP\_SERVICES.

```
$ HELP TCPIP_SERVICES
```

---

### Note

---

The word **command** refers to commands for the TCP/IP Services software. DCL commands and UNIX commands are explicitly identified.

---

Table 1-1 provides guidelines for using management control program commands.

# Using TCP/IP Services Management Commands

## 1.1 Entering Commands

Table 1–1 Management Command Guidelines

Element	Guideline
Address formats	<p>Some commands require that you specify one of the following kinds of addresses:</p> <ul style="list-style-type: none"><li>• IP</li><li>• Ethernet</li><li>• FDDI</li><li>• Token Ring</li><li>• Hardware</li></ul> <p>Be sure to use the appropriate format. The following examples illustrate an IP address, an Ethernet address, and a hardware address, respectively.</p> <pre>TCPIP&gt; SET HOST CROW /ADDRESS=1.2.3.4 TCPIP&gt; SET ARP AA-BB-04-05-06-07 CONDOR TCPIP&gt; SET BOOTP MACAW /HARDWARE=ADDRESS=08-dd-ff-2a-23-21</pre>
Default	<p>Refers to the command's behavior if optional qualifiers are omitted.</p>
File and directory names	<p>When you specify OpenVMS files, follow all OpenVMS file specification rules. Likewise, when you specify UNIX files, follow all UNIX file specification rules.</p>
Host names and IP addresses	<p>To specify a host or network name on a command line, you can enter either the host's name or the host's IP address.</p>
Keywords	<p>You can abbreviate commands to the fewest number of characters, usually four, that identify the command. The following command lines, for example, have identical meanings:</p> <pre>TCPIP&gt; SH SE NFS/FU/PER TCPIP&gt; SHOW SERVICE NFS /FULL /PERMANENT</pre> <p>Command examples shown in this manual are expressed using full command and qualifier names for clarity.</p>
Multiple values	<p>To specify multiple host names, addresses, or options for parameters and qualifiers, be sure to separate elements with commas and enclose the entire list in parentheses. Wildcards are valid unless otherwise stated. A space between multiple elements is optional unless otherwise stated. For example, the following qualifiers are the same:</p> <pre>/qualifier=(option_a:value1,option_b:value2,value3) /qualifier=(option_a=value1),(option_b=value2,value3)</pre> <p>Wildcards are valid unless otherwise stated. A space between multiple elements is optional unless otherwise stated.</p>

(continued on next page)

# Using TCP/IP Services Management Commands

## 1.1 Entering Commands

Table 1–1 (Cont.) Management Command Guidelines

Element	Guideline
Numeric values	<p>Unless otherwise stated, all numeric values are decimal. Values are indicated by either a preceding equals sign (=) or a colon (:). For example:</p> <pre>TCPIP&gt; SET NAME_SERVICE /SERVER:(SORA,JACANA,PARROT) - _TCPIP&gt; /ACCEPT:(HOSTS:JACANA,JAY,JUNCO,999.20.40.3)</pre>
Quotation marks	<p>On command lines, enclose the following in quotation marks when:</p> <ul style="list-style-type: none"><li>• Lowercase and mixed-case names that are to be stored in a database with the exact case preserved.</li><li>• Directory and file specifications that contain a slash (/).</li><li>• UNIX commands entered on the DCL command line.</li></ul> <p>Consider these examples:</p> <ol style="list-style-type: none"><li>1. To specify a path, enclose it in quotation marks: <pre>TCPIP&gt; MAP "/usr/songbirds/canary" CANARY\$DUA2:</pre></li><li>2. To specify host names using lowercase letters when you create a proxy entry in the database: <pre>TCPIP&gt; ADD PROXY COUSINS /GID=10 /UID=40 - _TCPIP&gt; /HOST=("raven","crow","rook","daw")</pre><p>Note the use of the DCL command-line continuation character (-) that allows you to continue a long command on the next line.</p></li><li>3. To specify a lowercase host name when adding the host to the hosts database, use these commands: <pre>TCPIP&gt; SET HOST "eaglet" /ADDRESS = 128.33.22.1 TCPIP&gt; SHOW HOST EAGLET</pre><p>Note that DCL interprets all input as uppercase unless you enclose it in quotation marks. Therefore, you must use quotation marks to enter the host name in lowercase in the hosts database. To display information about a host, you can enter either uppercase or lowercase characters.</p></li><li>4. Use quotes when entering a UNIX command at the DCL prompt. For example: <pre>\$ TCPIP "ifconfig -a"</pre></li></ol>
UNIX commands	<p>Follow UNIX syntax and case rules when entering UNIX commands at the TCPIP&gt; prompt. For example, enter the ifconfig command in lowercase letters:</p> <pre>TCPIP&gt; ifconfig options</pre> <p>The following use of the ifconfig command is incorrect:</p> <pre>TCPIP&gt; IFCONFIG options</pre>

(continued on next page)

# Using TCP/IP Services Management Commands

## 1.1 Entering Commands

**Table 1–1 (Cont.) Management Command Guidelines**

Element	Guideline										
Wildcards	<p>If you specify a wildcard on a command line, you are asked for confirmation before the command executes.</p> <p>You can change this default behavior with the /NOCONFIRM qualifier. For example:</p> <pre>TCPIP&gt; REMOVE PROXY GRACKLE/GID=*/UID=130</pre> <table border="1"> <thead> <tr> <th>VMS User_name</th> <th>Type</th> <th>User_ID</th> <th>Group_ID</th> <th>Host_name</th> </tr> </thead> <tbody> <tr> <td>GRACKLE</td> <td>N</td> <td>269</td> <td>48</td> <td>MAPLE</td> </tr> </tbody> </table> <p>Remove? [N]:</p>	VMS User_name	Type	User_ID	Group_ID	Host_name	GRACKLE	N	269	48	MAPLE
VMS User_name	Type	User_ID	Group_ID	Host_name							
GRACKLE	N	269	48	MAPLE							

### 1.1.1 Setting Configuration Parameters

Some commands allow you to enter information in the database; others modify only the run-time parameters. Table 1–2 shows the SET commands that affect one or the other.

**Table 1–2 SET Commands**

Modify Permanent Database Files	Modify Dynamic Memory
SET BOOTP	SET ARP
SET CONFIGURATION	SET COMMUNICATION
SET HOST	SET INTERFACE
SET MX_RECORDS	SET NAME_SERVICE
SET NETWORK	SET NFS_SERVER
SET CONTAINER	SET PROTOCOL
SET ROUTE	SET ROUTE
SET SERVICE	

Note that the SET ROUTE command affects both the permanent and dynamic routing databases.

### 1.1.2 Modifying the Configuration Database

Unlike the other databases, which have similar objects, the configuration database holds diverse initialization information for various TCP/IP Services components.

The following commands modify the configuration database:

- SET CONFIGURATION BIND
- SET CONFIGURATION COMMUNICATION
- SET CONFIGURATION ENABLE SERVICE
- SET CONFIGURATION INTERFACE
- SET CONFIGURATION NAME\_SERVICE
- SET CONFIGURATION PROTOCOL
- SET CONFIGURATION SMTP
- SET CONFIGURATION SNMP



## Using TCP/IP Services Management Commands

### 1.1 Entering Commands

- SET CONFIGURATION START ROUTING
- SET CONFIGURATION TIME

#### 1.1.3 Creating and Deleting Files

The CREATE commands create the following kinds of files:

- Database files  
Compaq strongly recommends that you use the TCP/IP Services configuration procedure (TCPIP\$CONFIG) instead of manually creating databases. See the *Compaq TCP/IP Services for OpenVMS Installation and Configuration* guide for instructions.

Use the following commands to create database files:

- CREATE BOOTP
  - CREATE CONFIGURATION
  - CREATE EXPORT
  - CREATE HOST
  - CREATE NETWORK
  - CREATE PROXY
  - CREATE ROUTE
  - CREATE SERVICE
- UNIX container directories  
These directories are used by the NFS server software. Use the following commands to create and delete container directories and files:
    - CREATE CONTAINER
    - DELETE CONTAINER
    - CREATE DIRECTORY
    - REMOVE DIRECTORY
    - REMOVE FILE

#### 1.1.4 Adding and Deleting Records

To add and delete records from the TCP/IP Services databases, use the CONVERT, ADD, and REMOVE management commands.

Use the following commands to add records to and delete records from the proxy and export databases:

- ADD EXPORT
- REMOVE EXPORT
- ADD PROXY
- REMOVE PROXY

You cannot modify information that you enter into databases. Instead, delete the record with the REMOVE command and then issue a new ADD command.

## Using TCP/IP Services Management Commands

### 1.1 Entering Commands

TCP/IP Services provides the following kinds of CONVERT management commands:

- **CONVERT/CONFIGURATION BIND**  
Converts BIND configuration information to BIND Version 8.1 format.
- **CONVERT/VMS**  
Populates an existing database with entries from a UNIX database file.
- **CONVERT/UNIX**  
Reads a TCP/IP Services database and converts the information to a UNIX-formatted (sequential) database file. For example, **CONVERT/UNIX HOST** reads the hosts database and converts the records into a UNIX-formatted `/etc/hosts` file.

#### 1.1.5 Starting and Stopping Software

You can start and stop software components interactively by using the following commands:

- **START MAIL**
- **START ROUTING**
- **STOP ROUTING**

For example:

```
TCPIP> START ROUTING /SUPPLY
```

For the server components that are started by the auxiliary server upon an incoming client request, the **ENABLE SERVICE** command tells the the auxiliary server to listen for requests and act upon them.

The **DISABLE SERVICE** command tells the auxiliary server to stop listening for incoming requests.

Use the following commands to set components to start when TCP/IP Services starts. The permanent configuration is stored in the configuration database.

- **SET CONFIGURATION ENABLE SERVICE**
- **SET CONFIGURATION ENABLE NOSERVICE**
- **SET CONFIGURATION START ROUTING**
- **SET CONFIGURATION START NOROUTING**

#### 1.1.6 Validating Data Integrity

Use the following commands to verify the integrity of TCP/IP Services files:

- **ANALYZE CONTAINER**
- **ANALYZE MAIL**
- **ANALYZE SERVICE**

### 1.1.7 Managing NFS

The NFS server requires the following management commands:

- MAP
- SET CONFIGURATION MAP
- SHOW MAP
- SHOW CONFIGURATION MAP
- UNMAP
- SET CONFIGURATION NOMAP
- SET NFS\_SERVER
- SHOW NFS\_SERVER
- CREATE EXPORT
- ADD EXPORT
- REMOVE EXPORT
- SET EXPORT
- SHOW EXPORT
- CREATE PROXY
- CONVERT/VMS PROXY
- ADD PROXY
- REMOVE PROXY
- SHOW PROXY

### 1.1.8 Using NFS

The TCP/IP Services software includes commands for using NFS. Use the following commands to view container file systems and to copy files to and from them:

- CREATE DIRECTORY
- DIRECTORY
- REMOVE DIRECTORY
- REMOVE FILE
- CREATE CONTAINER
- DELETE CONTAINER
- EXPORT
- IMPORT

For using the NFS client (working with files that reside on remote hosts), TCP/IP Services software provides the following commands:

- MOUNT
- SHOW MOUNT
- DISMOUNT

## Using TCP/IP Services Management Commands

### 1.1 Entering Commands

#### 1.1.9 Displaying Information

The SHOW and LIST commands display configuration, status, and performance information.

### 1.2 UNIX Management Commands

You can use UNIX management commands to manage the TCP/IP Services software. Table 1–3 describes the supported UNIX commands.

**Table 1–3 UNIX Management Commands**

Command	Description
ifconfig	Configures or displays network interface parameters, redefines an address for a particular interface, or sets options such as an alias list, broadcast address, or access filter.
netstat	Displays network statistics of sockets, data link counters, specified protocols or aliases, network interfaces, and a host's routing table.
sysconfig	Displays and maintains the network subsystem attributes.
route	Allows you to manipulate the routing table manually. Normally, a system routing table management component, such as GATED or ROUTED, will tend to this task.
arp	Controls and displays ARP tables for the specified host.
ripquery	Requests all routes known by a RIP gateway by sending a RIP request or a POLL command.
traceroute	Displays the route that packets take to a network host.

To use UNIX management commands at the DCL prompt, execute the command procedure SYSS\$MANAGER:TCPIP\$DEFINE\_COMMANDS.COM. For example:

```
$ @SYSS$MANAGER:TCPIP$DEFINE_COMMANDS
```

This command procedure defines process-specific commands that enable you to enter UNIX commands from the DCL prompt. Note that execution of a UNIX command in a DCL command procedure does not return an error in \$STATUS, so you cannot test for the failure of a UNIX command in a DCL command procedure.

The following command shows how to obtain information about an interface configured on your host. Note the use of quotation marks to preserve the case of the input:

```
$ ifconfig "WF0"
```

The following is displayed:

```
WF0: flags=c43<UP,BROADCAST,RUNNING,MULTICAST,SIMPLEX>  
rxmt 1000, reach time 30000, dad tries 1, MT 4352, hops 64, token len 64  
inet 16.20.208.100 netmask ffff0000 broadcast 16.20.255.255 ipmtu 4470  
inet6 fe80::200:f8ff:fe66:2e35
```

You must enclose uppercase options in quotation marks when entering UNIX commands at the DCL prompt.

## Using TCP/IP Services Management Commands

### 1.2 UNIX Management Commands

For more information about UNIX command options and flags, refer to the *Compaq TCP/IP Services for OpenVMS Tuning and Troubleshooting* manual, or enter `HELP unix_command` at the `TCPIP>` prompt. For example, to display information about the `netstat` command, enter:

```
TCPIP> HELP NETSTAT
```



---

## Command Descriptions

This chapter describes the TCP/IP Services management commands in alphabetical order.

For information about how to enter commands, see Chapter 1.

## ADD EXPORT

---

## ADD EXPORT

Adds an export entry, in the form of a UNIX path name, to the export database for a Network File System (NFS) file system. The path name is a name that is mapped to one of the following:

- An OpenVMS disk
- A subdirectory on an OpenVMS disk
- A UNIX container file system

**Related commands:** MAP, REMOVE EXPORT, SET CONFIGURATION MAP, SHOW EXPORT, SHOW HOST

**Applies to:** NFS server

### Format

```
ADD EXPORT "/path/name" /HOST=host
           [ /OPTIONS=
             [NO]DATA_CONVERSION
             [NO]NAME_CONVERSION
             [NO]PURGE_VERSIONS
             [NO]TYPELESS_DIRECTORIES ]
```

### Restrictions and Tips

This command requires read and write access to the export database. The following restrictions and instructions apply:

- Do not use wildcards within a UNIX directory specification.
- For each host, define both its host name and any alias names.
- For each entry, use uppercase and lowercase consistently.
- If you remove an export entry and replace the entry using different options; each client must dismount and remount for the new options to take effect.

### Parameters

***"/path/name"***

Required.

File system to add to the export database.

Separate directory and subdirectory names with slashes.

### Qualifiers

***/HOST=*host****

Required.

The NFS client host or hosts that will have access to the specified NFS file system.

You can use a wildcard to allow access to all hosts.



**/OPTIONS= { [NO]DATA\_CONVERSION |[NO]NAME\_CONVERSION  
|[NO]PURGE\_VERSIONS |[NO]TYPELESS\_DIRECTORIES }**  
Optional.

---

**Note**

---

For clients operating in OpenVMS to OpenVMS mode, the server ignores the options in the export record and uses the settings required for OpenVMS to OpenVMS mode.

---

Options for the specified directory:

- DATA\_CONVERSION, NODATA\_CONVERSION
  - DATA\_CONVERSION (default)
 

Converts the following kinds of sequential files:

    - \* Variable
    - \* Variable with fixed-length control (VFC)
    - \* Fixed-record formats

Converts sequential files according to the rules applied by the following record attributes:

    - \* Carriage return/carriage control (**CR**)
    - \* Fortran carriage control (**FTN**)
    - \* Print file-format control (**PRN**)

Stream formats are returned unconverted.

The data in files with nonstream records cannot be written back to the file.
  - NODATA\_CONVERSION
 

File data is considered raw and is returned without conversion. Nonstream records are returned with their record control information mixed with the record data. Files can be rewritten randomly.
- NAME\_CONVERSION, NONAME\_CONVERSION
  - NAME\_CONVERSION
 

A non-OpenVMS client can create files with mixed-case names and names containing characters that are invalid for OpenVMS file names. The server converts such names to valid OpenVMS file names, and reverses the conversion when displaying the file names to a non-OpenVMS client.
  - NONAME\_CONVERSION (default)
 

Clients can only create files with valid OpenVMS names. The server performs case-insensitive lookups and displays directories in lowercase.
- PURGE\_VERSIONS, NOPURGE\_VERSIONS
 

Default: NOPURGE\_VERSIONS

Deletes multiple versions of files. (The NFS CREATE and RENAME calls can create multiple versions. The NFS READDIR call can sense multiple versions.)

## ADD EXPORT

- TYPELESS\_DIRECTORIES, NOTYPELESS\_DIRECTORIES
  - TYPELESS\_DIRECTORIES

Removes `.dir.1` from the name of directories. A naming conflict could arise if, for example, two files exist in the parent directory:

```
DOVE.;1 (regular file)
DOVE.DIR;1 (directory file)
```

The name is returned as `dove.`, rather than `dove`, if a file and a conflicting directory exist.
  - NOTYPELESS\_DIRECTORIES (default)

Returns names as `file.ext` and `file.dir`.

### Examples

1. TCPIP> ADD EXPORT "/gold/finch" /HOST=GOLD  
**Adds the name of UNIX directory /gold/finch to the export database and gives NFS client users on the remote host gold access to this directory.**
2. TCPIP> ADD EXPORT "/gold/finch" /HOST=(PURPLE,FINCH)  
**Adds the directory /gold/finch to the export database and gives NFS client users on multiple remote hosts (PURPLE and FINCH) access to this directory.**

---

## ADD PROXY

Adds entries to the proxy database that give remote users an OpenVMS identity (account name). Applies to the NFS server, NFS client, PC-NFS, RSH, LPR/LPD, and customer-developed services.

The proxy database contains communication proxies and NFS proxies:

- Communication proxy
  - Provides an identity for users of RSH, RLOGIN, REXEC, RMT/RCD, LPR/LPD, and customer-written services, if these services are marked with SET SERVICE /FLAGS=APPLICATION\_PROXY.

---

### Note

---

The ROOT account does not require a communication proxy in the proxy database. The /FLAGS=APPLICATION\_PROXY flag, therefore, is not relevant when you are setting up a communication proxy for a UNIX root account.

---

- **Required qualifiers:** /HOST, /REMOTE\_USER.
- NFS proxy
  - Provides an identity for users of NFS client, NFS server, PC-NFS. No two proxies can have the same UID and host combination.
  - **Required qualifiers:** /HOST, /GID, /UID.

You can combine NFS and communication proxies in one record.

**Related commands:** SHOW HOST, DCL command AUTHORIZE, CONVERT/VMS PROXY, REMOVE PROXY, SHOW PROXY

### Format for Communication Proxies

```
ADD PROXY user { /HOST=host | /REMOTE_USER=user }
           [ /PERMANENT ]
```

### Format for NFS Proxies

```
ADD PROXY user { /GID=n | /HOST=host | /UID=n }
           [ /NFS=options ]
           [ /PERMANENT ]
```

### Restrictions and Tips

Requires read and write access to the proxy database and one of the following privileges:

- SYSPRV
- SYSLCK
- OPER

For each host, define both its host name and alias names.

## ADD PROXY

For each entry, use uppercase and lowercase consistently.

### Parameters

#### ***user***

Required.

Local OpenVMS identity for the user of: NFS server, NFS client, PC-NFS, remote shell, or LPR/LPD.

### Qualifiers

#### ***/GID=*n****

Required for an NFS proxy.

Group identifier (GID) for an NFS user.

Wildcards not allowed.

#### ***/HOST=*host****

Required.

Host name on which the NFS user is working.

- The host must be seen on the SHOW HOST/LOCAL display. It is important to use the SHOW HOST command to verify that the host is known to TCP/IP Services because ADD PROXY does not do this check.
- A wildcard is allowed.
- Compaq recommends that you define both the host name and any alias names.

#### ***/NFS=[ INCOMING | OUTGOING ]***

Optional. Default: /NFS=(INCOMING,OUTGOING).

Creates an NFS proxy for local clients, remote clients, or PC-NFS clients. Specify one of the following:

- /NFS=OUTGOING — Proxy to use NFS client
- /NFS=INCOMING — Proxy to use NFS server
- /NFS=(OUTGOING,INCOMING) — Proxy to use both NFS server and NFS client

#### ***/PERMANENT***

Optional. Default: Both permanent and volatile databases.

Adds the entry only to the permanent proxy database.

- Communication proxy
  - If REMOTE\_USER is not active, changes are made to the permanent database.
  - If REMOTE\_user is active, changes to the permanent database take effect after you restart RSH, RLOGIN, or LPD.

#### ***/REMOTE\_USER=*user****

Required for a communication proxy. Not valid on NFS proxy.

Specifies the remote client's user name.

A wildcard is allowed.

**/UID=*n***

Required for an NFS proxy.

Specifies the user identifier (UID) for an NFS user.

Wildcards are not allowed.

### Examples

1. TCPIP> ADD PROXY HAWAIIAN\_GOOSE /NFS=(OUTGOING,INCOMING) -  
\_TCPIP> /GID=10 /UID=444 /HOST="nene"

**Creates a proxy called HAWAIIAN\_GOOSE, authorizing use of both the NFS client and the NFS server to and from host nene.**

2. TCPIP> ADD PROXY COUSINS /GID=10 /UID=40 /NFS=OUTGOING -  
\_TCPIP> /HOST=("grackle","blackbird")

**Enters an NFS proxy called COUSINS for a local NFS client user named COUSINS. This user can access remote files from NFS servers grackle and blackbird.**

3. TCPIP> ADD PROXY REMOTE\_UGLY\_DUCKLING -  
\_TCPIP> /REMOTE\_USER="cygnet" /HOST="babyswan"

**Adds to the proxy database communication proxy REMOTE\_UGLY\_DUCKLING for remote user cygnet at host babyswan.**

## ANALYZE CONTAINER

---

### ANALYZE CONTAINER

Verifies the integrity of a UNIX container file, including the following checks:

- Superblock validation
- Inode validation
- Directory validation
- Internal allocation validation
- Directory hierarchy validation

Reports, and optionally corrects, problems within the structure of the container directory. Applies to the NFS server.

**Related commands:** DIRECTORY, SHOW CFS, MAP, UNMAP

#### Format

```
ANALYZE CONTAINER device:path.name
                  [ /[NO]CONFIRM ]
                  [ /[NO]REPAIR ]
```

#### Restrictions and Tips

- Before you enter the ANALYZE CONTAINER command, you must map the OpenVMS volume on which the container directory resides, using the MAP command.
- Before you enter the ANALYZE CONTAINER command, unmap the container file system to prevent users from attempting to access to it while you analyze it.
- This command requires the BYPASS privilege.

#### Parameters

***device:path.name***

Required.

Device and container directory to analyze.

#### Qualifiers

**/CONFIRM**

**/NOCONFIRM**

Optional. Default: /NOCONFIRM.

Use only with the /REPAIR qualifier.

When the software encounters a problem with the services database, it displays a description and solution and then requests confirmation before making each correction. For example:

## ANALYZE CONTAINER

```
%TCPIP-E-ANA_SUP_BADIICGSIZE, Problem: Bad initial inode cell group  
size:bad_value  
Solution: Will be replaced by default size: good_value  
CONFIRM [Y/N/G]:
```

In response to the CONFIRM: prompt, enter one of the following:

- Y to repair the problem
- N to ignore the problem
- G to change to NO CONFIRMATION mode

**/REPAIR**

**/NOREPAIR**

Optional. Default: /NOREPAIR.

Any errors will be repaired.

### Examples

1. TCPIP> UNMAP "/wren20"  
TCPIP> ANALYZE CONTAINER DUA0:[WREN20]

Verifies the integrity of container DUA0:[WREN20].

## ANALYZE MAIL

---

## ANALYZE MAIL

Verifies the consistency of the SMTP queues with SMTP control files.

**Related commands:** REMOVE MAIL, SHOW MAIL

### Format

```
ANALYZE MAIL [ user ]  
              [ /[NO]CONFIRM ]  
              [ /DELETE[=options] ]  
              [ /HOLD=time ]  
              [ /LOG=file ]  
              [ /[NO]REPAIR ]
```

### Restrictions

Requires SYSNAM, SYSPRV, or BYPASS privilege to access mail that is not yours.

### Parameters

***user***  
Optional. Default: All users.  
User whose mail you want to analyze.

### Qualifiers

**/CONFIRM**  
**/NOCONFIRM**  
Optional. Default: /NOCONFIRM

Use only with either the /REPAIR or the /DELETE qualifier.

When the software encounters a problem, it displays a description and solution. It then requests confirmation before making a correction or deleting each record. Enter one of the following:

- Y to repair the problem
- N to ignore the problem
- G to change to NO CONFIRMATION mode

**/DELETE [=BEFORE=*time* | =SINCE=*time*]**  
Optional. Default: Files not deleted.

Deletes each control file without a corresponding queue entry.

- =BEFORE=*time*
  - Deletes files created before the specified time.
  - Default: Current date and time.



- **=SINCE=*time***
  - Deletes files created since the specified time.
  - Default: Deletes all files.

Use the /DELETE and /REPAIR qualifiers on the same command line only if their time frames do not conflict.

The following command requeues lost mail created since yesterday and deletes all previous mail:

```
TCPIP> ANALYZE MAIL /REPAIR /DELETE=BEFORE=YESTERDAY
```

#### **/HOLD=*time***

Optional. Default: Immediate retransmission.

Hold, until the specified time, lost control files that you requeued.

#### **/LOG[=*file*]**

Optional. Default: [*current\_default\_dir*]:TCPIP\$SMTP\_ANALYZE.LOG.

Writes the ANALYZE MAIL log to the specified file.

#### **/REPAIR**

#### **/NOREPAIR [=BEFORE=*time* | =SINCE=*time*]**

Optional. Default: /NOREPAIR.

Corrects errors as follows:

- Resubmits for delivery each valid control file in the SMTP directory with no entry in an SMTP queue.
- Deletes each invalid control file (fails the internal consistency check) and the corresponding queue entry.
- Either requeues or deletes messages placed on hold.

Supports the following options:

- **=BEFORE=*time***
  - Deletes files created before the specified time.
  - Default: Current date and time.
- **=SINCE=*time***
  - Deletes files created since the specified time.
  - Default: Deletes all files.

Do not use /REPAIR with /DELETE if their time frames conflict.

## Examples

```
1. TCPIP> ANALYZE MAIL /REPAIR
```

Displays status for the SMTP queues, and requeues each valid control file that lacks a corresponding queue entry.

## ANALYZE MAIL

2. TCPIP> ANALYZE MAIL /DELETE

Creates the summary of SMTP queues, and deletes each valid control file that lacks a corresponding SMTP queue entry.

3. TCPIP> ANALYZE MAIL DRAKE /REPAIR /DELETE=BEFORE=24-SEP-2000

This command does the following:

- Creates a summary of SMTP entries and control files for user DRAKE.
- Requeues control files that lack corresponding queue entries.
- Deletes control files created before September 24, 2000.

---

## ANALYZE SERVICE

Searches through the services database for corrupted definitions. Displays invalid records and, with the /REPAIR qualifier, deletes them.

**Related commands:** SET SERVICE, SHOW SERVICE

### Format

```
ANALYZE SERVICE [ /[NO]CONFIRM ]
                [ /[NO]REPAIR ]
```

### Restrictions

Requires write access to the directory with the services database.

### Qualifiers

**/CONFIRM**

**/NOCONFIRM**

Optional. Default: /NOCONFIRM.

Use only with the /REPAIR qualifier.

When the software encounters a problem, it displays a description and a solution. It then requests confirmation before making a correction.

Respond to the CONFIRM: prompt by entering one of the following:

- Y to repair the problem
- N to ignore the problem
- G to change to NO CONFIRMATION mode

**/REPAIR**

**/NOREPAIR**

Optional. Default: /NOREPAIR

Deletes the corrupted records.

### Examples

```
1. TCP/IP> ANALYZE SERVICE
```

```

                Invalid IP option records
Service          Port  Proto  Process          Address
-----
TOE              25   TCP    TOED             0.0.0.0
NESTING         560   TCP    NEW_EGGS_TCPIP  0.0.0.0

IP option records
Total:           0
Invalid:         0

TCP option records
Total:           7
Invalid:         2
```

Displays total and invalid protocol option records found in two service definitions, TOE and NESTING.

## ANALYZE SERVICE

2. TCPIP> ANALYZE SERVICE /REPAIR /CONFIRM

Service	Port	Proto	Process	Address
TOE	67	UDP	TOED	0.0.0.0

Remove? [N]: YES

Service	Port	Proto	Process	Address
NESTING	69	UDP	NEW_EGGS_TCPIP	0.0.0.0

Remove? [N]: YES

**Displays the total protocol option records and deletes, after confirmation, the invalid records.**

---

## CONVERT/CONFIGURATION\_BIND

Converts the UCX BIND Version 4.x name server configuration to the BIND Version 8.1 format. Applies to the BIND name server. Use this command if you have a BIND configuration from an earlier release (Version 4.2 or lower) of the TCP/IP Services software. This command extracts the BIND configuration information from the file UCX\$CONFIGURATION.DAT and creates the ASCII file TCPIP\$BIND.CONF.

**Related commands:** SET CONFIGURATION BIND, SHOW CONFIGURATION BIND

### Format

CONVERT/CONFIGURATION BIND [*bind\_conf\_file*] [/CLUSTER=*lbroker\_conf\_file*]

### Parameters

***bind\_conf\_file***

Optional. Default: SYSSSPECIFIC:[TCPIP\$BIND]TCPIP\$BIND.CONF.

Specifies the alternate name or location of the BIND configuration file to be created.

### Qualifiers

***/CLUSTER=lbroker\_conf\_file***

Optional. Default: SYSSSYSDEVICE:[TCPIP\$LD\_BKR]TCPIP\$LBROKER.CONF

Creates the file used by the load broker for cluster load balancing. Here, *lbroker\_conf\_file* specifies the name of the load broker configuration file.

### Examples

1. TCPIP> CONVERT /CONFIGURATION BIND -  
\_TCPIP /CLUSTER=SYSSSYSDEVICE:[TCPIP\$LD\_BKR]TCPIP\$LBROKER.CONF

Converts the UCX BIND server configuration to BIND Version 8.1 format and creates the configuration file SYSSSPECIFIC:[TCPIP\$BIND]TCPIP\$BIND.CONF. The /CLUSTER qualifier creates the configuration file TCPIP\$LBROKER.CONF used by the load broker.

2. TCPIP> CONVERT /CONFIGURATION BIND SITE2\_BIND.CONF

Converts the UCX BIND server configuration and creates the configuration file SITE2\_BIND.CONF.

See the *Compaq TCP/IP Services for OpenVMS Management* guide for more information about the BIND name server, resolver, and load broker.

## CONVERT/UNIX BIND

---

### CONVERT/UNIX BIND

Creates a BIND server database and populates it with records from the local host and MX databases. This command will create either a forward translation file or a reverse translation file. If you specify a *domain.name* that ends in *IN-ADDR.arpa*, a reverse translation file is created.

**Related commands:** SET HOST, SET MX\_RECORD

#### Format

```
CONVERT/UNIX BIND /DOMAIN=domain.name [ /[[NO]LOG ]
```

#### Qualifiers

**/DOMAIN=*domain.name***

Required.

Domain for which to extract data. Determines whether to perform forward translation or reverse translation. The following restrictions and instructions apply:

- The domain name must be fully qualified.
- The closing dot is not required.
- Do not use wildcards.
- Specify up to four parts of the IP address for varying degrees of selectivity. For example:

*/DOMAIN=16.IN-ADDR.arpa* is less selective.

*/DOMAIN=8.20.16.IN-ADDR.arpa* is more selective.

The end of *domain.name* determines whether a forward or reverse translation is performed. For example:

- If the domain name ends in *IN-ADDR.arpa*:
  - Reverse translation is performed.
  - The domain is some part of an IP address, reversed, and added to *IN-ADDR.arpa*.
  - The selection includes the contents of the hosts database in the output.
- If the domain name ends in anything else (for example, */DOMAIN=DAW.MAG.COM*):
  - Forward translation is performed.
  - All hosts in *domain.name* or in any of its subdomains are selected for the output file.
  - CONVERT/UNIX BIND does a forward translation and selects hosts in *DAW.MAG.COM* and in its subdomains.

**/LOG**

**/NOLOG**

Optional. Default: /NOLOG.

Shows records as they are processed.

## Examples

1. TCPIP> CONVERT/UNIX BIND /DOMAIN=KESTREL.SMALL.FALCON

On host KESTREL, creates a BIND server database with default file name SYSSSPECIFIC:[TCPIP\$BIND]KESTREL\_SMALL\_FALCON.DB.

BIND and MX records for the host's domain, kestrel.small.falcon, are extracted, converted, and written to KESTREL\_SMALL\_FALCON.DB.

2. TCPIP> CONVERT/UNIX BIND /LOG /DOMAIN=ABC.COM

Creates a BIND server database. The /LOG qualifier indicates that records will be displayed as they are processed.

## CONVERT/UNIX HOST

---

## CONVERT/UNIX HOST

Reads the hosts database and converts the information to an ASCII file formatted for use as a hosts file on a UNIX system.

The name and location of the hosts database is specified by the logical name TCPIP\$HOST. If this name is not defined, the command looks for TCPIP\$HOST.DAT in your current directory.

**Related commands:** CREATE HOST, SET HOST, SHOW HOST

### Format

```
CONVERT/UNIX HOST [ destination_file ]  
                  [ /BYADDRESS ]  
                  [ /LOG ]
```

### Restrictions

Requires:

- Read access to the hosts database.
- Write access to [ ]ETC.HOSTS.

### Parameters

***destination\_file***

Optional. Default: [ ]ETC.HOSTS (UNIX formatted)

Allows you to specify the name for the new file.

### Qualifiers

**/BYADDRESS**

Optional. Default: Sorts by name.

Sorts entries in the converted file by IP address.

**/LOG**

Optional. Default: No display.

Interactively displays the processing.

### Examples

1. TCPIP> CONVERT/UNIX HOST

Converts the hosts database TCPIP\$HOST to an ASCII file that is formatted for use as a hosts file on a UNIX system. The resulting file is named (default) ETC.HOSTS in the current directory and can be used on a UNIX system as the file `/etc/hosts`.



---

## CONVERT/UNIX NETWORK

Converts the networks database to an ASCII file formatted for use on a UNIX system.

The name and location of the networks database is specified by the logical name TCPIP\$NETWORK. If this name is not defined, the command looks for TCPIP\$NETWORK.DAT in your current directory.

**Related commands:** CREATE NETWORK, SET NETWORK, SHOW NETWORK

### Format

```
CONVERT/UNIX NETWORK [ destination_file ]
                    [ /BYADDRESS ]
                    [ /LOG ]
```

### Restrictions

Requires:

- Read access to the hosts database.
- Write access to the file [ ]ETC.NETWORKS.

### Parameters

***destination\_file***

Optional. Default: [ ]ETC.NETWORKS (UNIX formatted).

Specifies the name of the new UNIX formatted file.

### Qualifiers

**/BYADDRESS**

Optional. Default: Sorts by name.

Sorts the converted file by network number.

**/LOG**

Optional. Default: No display.

Displays messages generated during processing.

### Examples

1. TCPIP> CONVERT/UNIX NETWORK /LOG

Converts the networks database (TCPIP\$NETWORK) to the ASCII file [ ]ETC.NETWORKS. This resulting file can be used as a networks database file /etc/networks on a UNIX system. The /LOG qualifier displays each record as it is converted.

2. TCPIP> CONVERT/UNIX NETWORK NETWORKS.TXT

Converts the networks database (TCPIP\$NETWORK) to the ASCII file [ ]NETWORKS.TXT. The resulting file may be used as the networks database file /etc/networks on a UNIX system.

## CONVERT/VMS BOOTP

---

### CONVERT/VMS BOOTP

Populates the existing BOOTP database with entries from a BIND-formatted UNIX `/etc/bootptab` file.

If the logical name `TCPIP$BOOTP` is defined, it is used to specify the directory and file name for the database. If `TCPIP$BOOTP` is not defined, the database is created as `[current_directory]TCPIP$BOOTP.DAT`.

**Related commands:** CREATE BOOTP, SET BOOTP, SHOW BOOTP

#### Format

```
CONVERT/VMS BOOTP [ source_file ]  
                  [ /ADD_HOST ]  
                  [ /FILE=sys_image_file ]
```

#### Restrictions

Requires:

- Read and write access to the hosts database (if using `/ADD_HOST` qualifier).
- Read access to the hosts database.

#### Parameters

***source\_file***

Optional. Default: `[]ETC.BOOTPTAB` in your current directory.

File to be converted.

#### Qualifiers

***/ADD\_HOST***

Optional. Default: No adding.

Adds new host names found in the UNIX `/etc/bootptab` file to `TCPIP$HOST.DAT`.

***/FILE=sys\_image\_file***

Optional. Default: None.

Specifies the name of the client's system image file to download if this file name is not in the BOOTP database.

#### Examples

```
1. TCPIP> CONVERT/VMS BOOTP BOOTP.DAT /ADD_HOST
```

Converts a UNIX ASCII boot data file to an OpenVMS indexed file. `BOOTP.DAT` specifies the source UNIX boot file to convert. For new hosts, the `/ADD_HOST` qualifier adds the host to the hosts database.

---

## CONVERT/VMS HOST

Populates the existing hosts database with entries from a UNIX `/etc/hosts` file.

The name and location of the hosts database is specified by the logical name `TCPIP$HOST`. If this name is not defined, the command looks for `TCPIP$HOST.DAT` in your current directory.

**Related commands:** CREATE HOST, SET HOST, SHOW HOST

### Format

```
CONVERT/VMS HOST [ source_file ]
                  [ /LOG ]
                  [ /UPCASE ]
```

### Restrictions

Requires:

- Read and write access to the hosts database.
- Read access to the UNIX formatted hosts file.
- Exclusive use of the hosts database.

### Parameters

***source\_file***

Optional. Default: `ETC.HOSTS` in your current directory.

UNIX formatted file to be converted to the `TCPIP$HOST` database file.

### Qualifiers

**/LOG**

Optional. Default: No logging.

Displays records as they are being processed.

**/UPCASE**

Optional. Default: Not created.

Creates an uppercase alias name for each host.

### Examples

1. `TCPIP> CONVERT/VMS HOST`

Converts the UNIX formatted hosts database file to the file `TCPIP$HOST.DAT`. The name of the UNIX formatted file is `ETC.HOSTS` in your current directory.

2. `TCPIP> CONVERT/VMS HOST HOSTS.TXT`

Converts the UNIX formatted hosts database file `HOSTS.TXT` to the file `TCPIP$HOST.DAT`.

## CONVERT/VMS NETWORK

---

## CONVERT/VMS NETWORK

Populates the existing networks database with entries from a UNIX `/etc/networks` file.

The name and location of the networks database is specified by the logical name `TCPIP$NETWORK`. If this name is not defined, the command looks for `TCPIP$NETWORK.DAT` in your current directory.

**Related commands:** CREATE NETWORK, SET NETWORK, SHOW NETWORK

### Format

```
CONVERT/VMS NETWORK [ source_file ]  
                    [ /LOG ]  
                    [ /UPCASE ]
```

### Restrictions

Requires:

- Read and write access to the networks database.
- Read access to `[ ]ETC.NETWORKS`.
- Exclusive use of the networks database.

### Parameters

***source\_file***

Optional. Default: `ETC.NETWORKS` in your current directory.

Name of the file to be converted.

### Qualifiers

**/LOG**

Optional. Default: Log file created.

Interactively displays records as they are being processed.

**/UPCASE**

Optional. Default: Alias not created.

Specifies that an uppercase alias name be created for each network name.

### Examples

1. `TCPIP> CONVERT/VMS NETWORK`

Converts a UNIX formatted `/etc/networks` database file into a TCP/IP Services formatted networks database. The OpenVMS file name of `/etc/networks` is `ETC.NETWORKS` in your current directory.

2. `TCPIP> CONVERT/VMS NETWORK /UPCASE`

Converts a UNIX formatted database file to a TCP/IP Services formatted networks database. An uppercase alias name is created for each network name.

---

## CONVERT/VMS PROXY

Populates the existing proxy database with entries from a UNIX `/etc/passwd` file.

The name of the proxy database is specified by the logical name `TCPIP$PROXY`. If this name is not defined, the command looks for `TCPIP$PROXY.DAT` in your current directory.

**Related commands:** `ADD PROXY`, `CREATE PROXY`

**Applies to:** NFS server, NFS client, PC-NFS

### Format

```
CONVERT/VMS PROXY [ source_file ] [ /LOG ]
```

### Restrictions

Requires:

- Read and write access to the proxy database.
- Read access to `[]ETC.PASSWORD`.
- Exclusive use of the proxy database.

### Parameters

***source\_file***

Optional. Default: `ETC.PASSWD` in your current directory.

ASCII file to convert to a TCP/IP Services proxy database.

### Qualifiers

**/LOG**

Optional. Default: No display.

Displays records as they are being processed.

### Examples

1. `TCPIP> CONVERT/VMS PROXY`

Converts a UNIX formatted `/etc/passwd` file to an OpenVMS formatted proxy database. The OpenVMS file name of `/etc/passwd` is `ETC.PASSWD` in your current directory.

2. `TCPIP> CONVERT/VMS PROXY UNIX_PASSWDS.TXT`

Converts a UNIX formatted `/etc/passwd` file to an OpenVMS formatted proxy database. In this example, the file `UNIX_PASSWDS.TXT` contains the `/etc/passwd` data.

## CREATE BOOTP

---

## CREATE BOOTP

Creates an empty BOOTP database, TCPIP\$BOOTP.DAT, located in SYSS\$COMMON:[SYSEXE].

If the logical name TCPIP\$BOOTP is defined, CREATE BOOTP uses the definition to create the directory and file name for the BOOTP database. If TCPIP\$BOOTP is not defined, the database is created as [*current.directory*]TCPIP\$BOOTP.DAT.

**Related commands:** CONVERT/VMS BOOTP, SET BOOTP

### Format

```
CREATE BOOTP
```

### Restrictions

Requires write access to the directory with the BOOTP configuration database. (Default directory is SYSS\$COMMON:[SYSEXE].)

---

**Caution**

---

Do not execute this command unless you intend to reconfigure your entire cluster.

---

### Examples

1. TCPIP> CREATE BOOTP

Creates the empty BOOTP database  
SYSS\$COMMON:[SYSEXE]TCPIP\$BOOTP.DAT.

---

## CREATE CONFIGURATION

Creates an empty configuration database, TCPIP\$CONFIGURATION.DAT, located in SYSS\$COMMON:[SYSEXE].

If the logical name TCPIP\$CONFIGURATION is defined, CREATE CONFIGURATION uses the definition to create the directory and file name for the configuration database. If TCPIP\$CONFIGURATION is not defined, the database is created as SYSS\$COMMON:[SYSEXE]TCPIP\$CONFIGURATION.DAT.

### Format

```
CREATE CONFIGURATION
```

### Restrictions

Requires write access to the directory with the configuration database.

---

**Caution**

---

Do not execute this command unless you intend to reconfigure your entire cluster.

---

### Examples

1. TCPIP> CREATE CONFIGURATION

Creates the empty configuration database  
SYSS\$COMMON:[SYSEXE]TCPIP\$CONFIGURATION.DAT.

## CREATE CONTAINER

---

## CREATE CONTAINER

Creates a UNIX file system with:

- An empty OpenVMS style root directory
- An empty local directory that corresponds to the UNIX root directory
- A container file in the OpenVMS style root directory

**Applies to:** NFS server

### Format

```
CREATE CONTAINER device:directory [ /HOST=host ]  
                [ /[NO]LOG ]  
                [ /OWNER=uic ]  
                [ /ROOT_MODE=n ]  
                [ /SIZE=option=value ]  
                [ /UID=n ]  
                [ /USER_NAME=vms_user_name ]
```

### Restrictions

Requires:

- Read and write access to the specified device and directory.
- SYSPRV or BYPASS privilege.

### Parameters

***device:directory***

Required.

Device and directory of the UNIX container.

### Qualifiers

**/HOST=*host***

Required. Default: None.

If the proxy database has multiple entries with the same user name and UID, the NFS server selects the entry specified with this qualifier.

**/LOG**

**/NOLOG**

Optional. Default: Displays host, UID, GID, and user name.

Displays a full description of the specified proxy database record for you to determine ownership (see /USER\_NAME).

**/OWNER=*uic***

Optional. Default: UIC in the selected proxy record.

OpenVMS ownership of the container file directory and container file.

(The other files in this directory are owned by the OpenVMS users whose proxy database entries correspond to the UNIX owner UIDs of the individual files.)



**/ROOT\_MODE=*n***

Optional. Default: 755 (provides the following protection for owner, group, and world rwx-rx-rx).

UNIX protection of the default container files: root directory, bit map, and superblock.

Specify octal values in the following order: for user, for group, for others. The values are:

- 0 — No access
- 1 — Execute access
- 2 — Write access
- 3 — Write and execute access
- 4 — Read access
- 5 — Read and execute access
- 6 — Read and write access
- 7 — Read, write, and execute access

For example, /ROOT\_MODE=751 provides:

User	Read, write, and execute access	7	rwx
Group	Read and execute access	5	rx
Other	Execute access	1	x

**/SIZE=*option=value***

Optional. Default: /SIZE=(INITIAL=8917,EXTEND=160,MAXIMUM=0).

Specifies the following file size attributes:

- INITIAL  
Specifies the initial size, in OpenVMS blocks, of the container. Maximum value: 8917.
- EXTEND  
When an extension is necessary, specifies the number of blocks by which the container is extended. Maximum value: 8192.

---

**Note**

---

Using large values might impact system performance and disk usage. In most cases, the default is sufficient.

---

- MAXIMUM  
Specifies the maximum size of the container.  
If the value is zero, the size of the container file can increase without limits.

**/UID=*n***

Optional. Default: UID in the selected proxy record.

Specifies the owner of the UNIX container root directory.

## CREATE CONTAINER

**/USER\_NAME=vms\_user\_name**

Required.

Specifies the user name of the owner of the container file system. The user name must be in the proxy database. The specified user becomes the owner of the internal root directory of the container.

### Examples

```
1.  TCPIP> CREATE CONTAINER DUCK$4:[DUCKLING] /HOST=MALLARD -  
    _TCPIP> /OWNER=[300,12] /ROOT_MODE=755 /UID=7015 -  
    _TCPIP> /USER_NAME=G_JONES
```

Creates container directory DUCK\$4:[DUCKLING]. The local OpenVMS owner is [300,12]. Remote users see the root directory as owned by UID 7015. The root directory is writable only by UID 7015; it is readable and executable by all others. Before you execute this command, user G\_JONES should have both an OpenVMS account with UIC [300,12] and an incoming proxy record specifying UID 7015 on host MALLARD.

---

## CREATE DIRECTORY

Creates a directory within an existing UNIX container.

**Applies to:** NFS server

**Related commands:** DIRECTORY, REMOVE DIRECTORY

### Format

```
CREATE DIRECTORY "/path/name" [ /HOST=host ]
                [ /[NO]LOG ]
                [ /MODE=n ]
                [ /UID=n ]
                [ /USER_NAME=vms_user_name ]
```

### Restrictions

Requires:

- Read and write access to the parent directory.
- SYSPRV or BYPASS privilege if you specify /USER\_NAME with a name other than your own.

The container file system must be mapped with the MAP command.

### Parameters

**"/path/name"**

Required.

Name of the directory you want to create.

### Qualifiers

**/HOST=host**

Optional. Default: Uses the first user name found.

If the proxy database has multiple entries with the same user name and UID combination, the value of /HOST determines the specified record.

**/LOG**

**/NOLOG**

Optional. Default: Displays values for host, UID, GID, and user name.

Displays a full description of the specified proxy database record for you to determine ownership (see /USER\_NAME).

**/MODE=n**

Optional. Default: 755 (provides the following protection for owner, group, and world: rwx-rx-rx).

UNIX protection of the new directory.

Specify octal values in the following order: for user, for group, for others. The values are:

- 0 — No access
- 1 — Execute access

## CREATE DIRECTORY

- 2 — Write access
- 3 — Write and execute access
- 4 — Read access
- 5 — Read and execute access
- 6 — Read and write access
- 7 — Read, write, and execute access

For example, `/MODE=751` provides:

User	Read, write, and execute access	7	rx
Group	Read and execute access	5	rx
Other	Execute access	1	x

### **`/UID=n`**

Optional. Default: None.

Entry in the proxy database that determines, if necessary, the ownership of the container root directory.

In the proxy database:

- UID and GID fields determine the root directory's UNIX identity.
- User name field determines the OpenVMS ownership.

Required to access an entry in the proxy database that lacks a unique UID, user name, and host combination.

You can use `/UID` with the `/HOST` and `/USER_NAME` qualifiers. If you do not have `SYSPRV` or `BYPASS` privilege, the values you specify must correspond to the values for your user name in the proxy database.

### **`/USER_NAME=vms_user_name`**

Optional. Default: `UID=0` and `GID=1` (if you have `SYSPRV` or `BYPASS` privilege).

Selects an entry in the proxy database and creates the UID, GID, and OpenVMS UIC for the directory files.

To select a user name that has a UIC different than the UIC of the process running the management program, you need `SYSPRV` or `BYPASS` privilege.

You can use `/USER_NAME` in combination with `/HOST` and `/UID`. However, if you do not have `SYSPRV` or `BYPASS` privilege, the values you specify must correspond to the values for your user name in the proxy database.

## Examples

1. 

```
TCPIP> MAP "/user" dua0:[group_a]
TCPIP> CREATE DIRECTORY "/user/umbrella.bird"
```

Creates a UNIX directory for user UMBRELLA called `umbrella.bird`.

In this example, the user UMBRELLA is running the TCP/IP Services management program from the directory (`[UMBRELLA.BIRD]`). The UIC for `[UMBRELLA]` is `[340,6]` and the `TCPIP$PROXY` entry is defined as follows:

## CREATE DIRECTORY

User	UID	GID	Host
UMBRELLA	300	12	*
SYSTEM	0	1	*

If UMBRELLA does not have SYSPRV or BYPASS privilege, the directory is created as follows:

UID = 300  
GID = 12  
UIC = [340,6]

If UMBRELLA has SYSPRV or BYPASS privilege, the directory is created as follows:

UID = 0  
GID = 1  
UIC = [SYSTEM]

## CREATE EXPORT

---

### CREATE EXPORT

Creates an empty export database file.

If the logical name TCPIP\$EXPORT is defined, CREATE EXPORT uses the definition to create the directory and file name for the export database. If TCPIP\$EXPORT is not defined, the database is created as SYSS\$COMMON:[SYSEXE]TCPIP\$EXPORT.DAT.

**Related commands:** ADD EXPORT, SHOW EXPORT

**Applies to:** NFS server

#### Format

```
CREATE EXPORT
```

#### Restrictions

Requires write access to the directory with the export database.

---

**Caution**

---

Do not execute this command unless you intend to reconfigure your entire cluster.

---

#### Examples

1. TCPIP> CREATE EXPORT

Creates an empty export database.

---

## CREATE HOST

Creates a hosts database file with:

- One entry for LOCALHOST
- LOCALHOST's alias, *localhost*
- LOCALHOST's address, 127.0.0.1

If the logical name TCPIP\$HOST is defined, CREATE HOST uses the definition to create the directory and file name for the hosts database. If TCPIP\$HOST is not defined, the database is created as SYSS\$COMMON:[SYSEXE]TCPIP\$HOST.DAT.

**Related commands:** SET HOST, SHOW HOST, CONVERT/VMS HOST

### Format

CREATE HOST

### Restrictions

Requires:

- Write access to the directory with the hosts database.
- Read and write access to the hosts database.

---

**Caution**

---

Do not execute this command unless you intend to reconfigure your entire cluster.

---

### Examples

1. TCPIP> CREATE HOST

Creates a hosts database with one entry for LOCALHOST.

## CREATE NETWORK

---

## CREATE NETWORK

Creates an empty networks database file.

If the logical name TCPIP\$NETWORK is defined, CREATE NETWORK uses the definition to create the directory and file name for the networks database. If TCPIP\$NETWORK is not defined, the database is created as SYSS\$COMMON:[SYSEXE]TCPIP\$NETWORK.DAT.

**Related commands:** SET NETWORK, SHOW NETWORK, CONVERT/VMS NETWORK

### Format

```
CREATE NETWORK
```

### Restrictions

Requires write access to the directory with the networks database.

---

**Caution**

---

Do not execute this command unless you intend to reconfigure your entire cluster.

---

### Examples

1. TCPIP> CREATE NETWORK  
Creates an empty networks database.



---

## CREATE PROXY

Creates an empty proxy database file.

If the logical name TCPIP\$PROXY is defined, CREATE PROXY uses the definition to create the directory and file name for the proxy database. If TCPIP\$PROXY is not defined, the database is created as SYSS\$COMMON:[SYSEXE]TCPIP\$PROXY.DAT.

**Related commands:** ADD PROXY, SHOW PROXY, CONVERT/VMS PROXY

### Format

```
CREATE PROXY
```

### Restrictions

Requires write access to the directory with the proxy database.

---

**Caution**

---

Do not execute this command unless you intend to reconfigure your entire cluster.

---

### Examples

1. TCPIP> CREATE PROXY  
Creates an empty proxy database.

## CREATE ROUTE

---

### CREATE ROUTE

Creates an empty permanent routes database file.

If the logical name TCPIP\$ROUTE is defined, CREATE ROUTE uses the definition to create the directory and file name for the routes database. If TCPIP\$ROUTE is not defined, the database is created as SYS\$COMMON:[SYSEXE]TCPIP\$ROUTE.DAT.

**Related commands:** SET ROUTE, SHOW ROUTE

#### Format

```
CREATE ROUTE
```

#### Restrictions

Requires write access to the directory with the routes database.

---

**Caution**

---

Do not execute this command unless you intend to reconfigure your entire cluster.

---

#### Examples

1. TCPIP> CREATE ROUTE

Creates an empty routes database file TCPIP\$ROUTE.DAT in the directory SYS\$COMMON:[SYSEXE].

---

## DEFINE COMMUNICATION\_CONTROLLER

Adds new mapping correspondence to the internal TCP/IP Services table. Use this command to add support for new communication controller devices that are added to an OpenVMS system after the latest release of TCP/IP Services is installed.

**Related commands:** LIST COMMUNICATION\_CONTROLLER, DELETE COMMUNICATION\_CONTROLLER, all INTERFACE commands

### Format

```
DEFINE COMMUNICATION_CONTROLLER controller
                                /INTERNET_INTERFACE=character
                                /TYPE=options
                                [ /DESCRIPTION=text ]
```

### Parameters

***controller***

Required.

Specifies the OpenVMS device name of the communication controller (as displayed by the DCL command SHOW DEVICE).

You must specify the controller. For examples of controllers with their corresponding device names, see the LIST COMMUNICATION\_CONTROLLER command. See the *Compaq TCP/IP Services for OpenVMS Management* guide for more information.

### Qualifiers

***/DESCRIPTION=text***

Optional. Default: None.

Specifies entry. For example, specify the device's name, such as DEFZA or DEUNA.

You can modify this value.

***/INTERNET\_INTERFACE=character***

Required.

Specifies the first letter of the interface name. The second character of the two-character interface name is automatically assigned, depending on what you specify for the /TYPE qualifier. If you prefer a standard name, call your Compaq support representative. If a standard interface name is not important, you can use any unique alphabetic character for this first character.

***/TYPE=options***

Required.

Specifies the controller type and implies the second character of the interface name. You must specify one of the following: Ethernet, FDDI, PPP, Serial or Token\_Ring. You can specify only one type at a time. If you specify Ethernet, then the implied second character of the interface name is E. If you specify FDDI, then the implied second character of the interface name is F. If you specify PPP, then the implied second character of the interface name is P. If you specify

## DEFINE COMMUNICATION\_CONTROLLER

Serial, then the implied second character of the interface name is L. If you specify Token\_Ring, then the implied second character of the interface name is T.

To change this definition, enter the following command:

### Examples

```
1. TCPIP> DEFINE COMMUNICATION_CONTROLLER controller -  
   _TCPIP> /TYPE=([NO]old_type,new_type)
```

The *old\_type*,*new\_type* options are:

- CLUSTER
  - The interface can join an internet cluster. To do this, also issue SET INTERFACE /CLUSTER.
  - You can specify CLUSTER with a controller type, for example, /TYPE=(ETHERNET,CLUSTER).
- [NO]ETHERNET
- [NO]FDDI
- [NO]TOKEN\_RING

```
2. TCPIP> DEFINE COMMUNICATION_CONTROLLER XE -  
   _TCPIP> /INTERNET_INTERFACE=D /TYPE=(ETHERNET,CLUSTER) -  
   _TCPIP> /DESCRIPTION=DEUNA
```

Defines interface D as the OpenVMS device XE.

---

## DELETE COMMUNICATION\_CONTROLLER

Deletes an entry for a communication controller from the configuration file.

**Related commands:** DEFINE COMMUNICATION\_CONTROLLER, LIST COMMUNICATION\_CONTROLLER

### Format

```
DELETE COMMUNICATION_CONTROLLER [ controller ]
                                [ /[NO]CONFIRM ]
                                [ /INTERNET_INTERFACE=character ]
```

### Restrictions

Requires OPER privilege.

### Parameters

***controller***

Optional. Default: All devices.

OpenVMS device name of the communication controller (as displayed by the DCL command SHOW DEVICE).

Specify the controller name that you entered with the DEFINE COMMUNICATION\_CONTROLLER command.

### Qualifiers

***/INTERNET\_INTERFACE=character***

Optional. Default: All letters.

Deletes the specified letter (which represents the first letter of an interface name).

***/CONFIRM***

***/NOCONFIRM***

Optional. Default: /CONFIRM if you use a wildcard.

Displays a message asking you to confirm the delete request.

### Examples

1. TCPIP> DELETE COMMUNICATION\_CONTROLLER EZ

Deletes all the entries for the Ethernet controller with device name EZ.

2. TCPIP> DELETE COMMUNICATION\_CONTROLLER -  
\_TCPIP /INTERNET\_INTERFACE=E

Deletes all the communication controller entries with an Internet interface name that begins with the letter E from the table used to match OpenVMS device names with Internet interface names.

## DELETE CONTAINER

---

### DELETE CONTAINER

Deletes a container file system and all its contents.

**Applies to:** NFS server

**Related commands:** CREATE CONTAINER, SHOW CFS

#### Format

DELETE CONTAINER *container\_file\_system*

#### Restrictions

Wildcards are not allowed.

Requires both read and delete access to the directory.

Requires BYPASS privilege.

#### Parameters

***container\_file\_system***

Required.

Device and directory name of the container file (no wildcards).

The container file has file type .CONTAINER.

#### Examples

1. TCPIP> DELETE CONTAINER WORK1\$:[DOVE.NEST\_BUILDING]

Deletes the container directory WORK1\$:[DOVE.NEST\_BUILDING] along with the container file, all subdirectories, and files.

---

## DIRECTORY

Displays a list of files, along with typical directory information, in a UNIX container directory.

**Applies to:** NFS server

### Format

```
DIRECTORY "/path/name" [ /FULL ] [ /VMS ]
```

### Restrictions

Requires:

- Read access to the specified container directory.
- BYPASS privilege.

### Parameters

**"/path/name"**

Required.

Name of the UNIX container directory for which you want a directory listing and, optionally, directory names.

### Qualifiers

**/FULL**

Optional. Default: Brief display.

Displays a comprehensive list of information, including the OpenVMS file name, for each file.

**/VMS**

Optional. Default: No OpenVMS file names provided.

Provides the corresponding OpenVMS file name for each file.

### Examples

1. TCPIP> DIRECTORY/FULL "/nest\_container"

```
Directory: /nest_container
```

```
.
OpenVMS file: _$1$DISK:[SYSTEM.NEST.HATCHLING]00012301$BFS.DIR;1
Size                               File ID: 74497
  Blocks:                4           Owner
  Bytes:                 1915        UID: 0
Created: 1-NOV-1997 13:17:18.91     GID: 1
Revised: 1-NOV-1997 13:17:19.24     Mode: 755 Type: Directory
Accessed: 1-NOV-1997 13:16:20.52    Links: 2
```

## DIRECTORY

```
..
OpenVMS file: _$1$DISK:[SYSTEM.NEST.HATCHLING]00012301$BFS.DIR;1
Size                               File ID: 74497
Blocks:                             4           Owner
Bytes:                             1915        UID: 0
Created: 1-NOV-1997 13:17:18.91   GID: 1
Revised: 1-NOV-1997 13:17:19.24   Mode: 755 Type: Directory
Accessed: 1-NOV-1997 13:16:20.52  Links: 2

.SUPER.SYS
OpenVMS file: no corresponding file
Size                               File ID: 6145
Blocks:                             1           Owner
Bytes:                             54          UID: 0
Created: 1-NOV-1997 13:17:18.91   GID: 1
Revised: 1-NOV-1997 13:17:17.24   Mode: 644 Type: File
Accessed: 1-NOV-1997 13:16:18.52  Links: 1

.BITMAP.SYS
OpenVMS file: no corresponding file
Size                               File ID: 6657
Blocks:                             16          Owner
Bytes:                             8187        UID: 0
Created: 1-NOV-1997 13:17:18.91   GID: 1
Revised: 1-NOV-1997 13:17:17.24   Mode: 644 Type: File
Accessed: 1-NOV-1997 13:16:18.52  Links: 1

.HISTORY.SYS
OpenVMS file: no corresponding file
Size                               File ID: 66305
Blocks:                             1           Owner
Bytes:                             129         UID: 0
Created: 1-NOV-1997 13:17:18.91   GID: 1
Revised: 1-NOV-1997 13:17:17.24   Mode: 644 Type: File
Accessed: 1-NOV-1997 13:16:18.52  Links: 1
```

**Displays a full directory listing of the container file system /nest\_container.**

2. TCPIP> DIRECTORY "/dove/nest/plans"

**Displays names of the files in UNIX directory /dove/nest/plans.**



---

## DISABLE SERVICE

For most services, this command disables the specified service but does not stop the current process. This allows you to perform an orderly shutdown of the service, which prevents new connections while allowing current connections to continue.

To stop and restart the current process:

1. Wait until the process exits, or stop it using the service-specific shutdown command procedure (TCPIP\$*service*\_SHUTDOWN.COM).
2. Restart the service using the service-specific startup command procedure (TCPIP\$*service*\_STARTUP.COM).

Note that, for the NFS server, TELNET, and RLOGIN, the DISABLE SERVICE command stops the current process.

**Related commands:** ENABLE SERVICE, SET SERVICE, SHOW SERVICE

### Format

```
DISABLE SERVICE service
                [ /ADDRESS=IP_address ]
                [ /PORT=n ]
                [ /PROCESS=process ]
                [ /PROTOCOL=protocol ]
```

### Parameters

***service***

Required.

Service you want to disable. Specify any service that appears in the SHOW SERVICE display. To disable all services, use a wildcard.

### Qualifiers

***/ADDRESS=IP\_address***

Optional. Default: 0.0.0.0.

Disables only the services for the specified address.

***/PORT=n***

Optional. Default: All ports.

Disables the service communicating at the specified port.

***/PROCESS=process***

Optional. Default: All processes.

Disables the service running as the specified process.

***/PROTOCOL=protocol***

Optional. Default: All protocols.

Disables only the services that use the specified protocol.

## DISABLE SERVICE

### Examples

1. TCPIP> DISABLE SERVICE TELNET

**Disables TELNET.**

2. TCPIP> DISABLE SERVICE RLOGIN /ADDRESS=130.180.4.7

**Disables the remote login process that is bound to address 130.180.4.7.**

---

## DISCONNECT DEVICE\_SOCKET

Interactively terminates a TCP/IP connection.

### Format

DISCONNECT DEVICE\_SOCKET *dev\_sock\_number*

### Parameters

***dev\_sock\_number***

Required.

Number of the device socket associated with the connection you want to terminate.

### Examples

1. TCP/IP> DISCONNECT DEVICE\_SOCKET BG123

Interactively terminates the connection at DEVICE\_SOCKET BG123.

## DISMOUNT

---

## DISMOUNT

Makes a physically remote file system that is currently accessible to local users inaccessible.

Dismounts a remote file system or directory from local device *DNFSn*: (the mount point).

Required order of command keywords: the DISMOUNT keyword, immediately followed by *mount\_point*. Example: DISMOUNT DNFS03:.

**Related commands:** MOUNT, SHOW MOUNT

**Applies to:** NFS client

### Format

```
DISMOUNT { mount_point | logical_name }  
          [ /ALL ]  
          [ /HOST=host ]  
          [ /[NO]WAIT ]
```

### Restrictions

Dismounting a /SYSTEM mount requires SYSNAM privilege.

Dismounting a /GROUP mount requires GRPNAM privilege.

### Parameters

#### *mount\_point*

Required (if you omit *logical\_name* and the /ALL qualifier). Default: None.

DNFS device (and optional directory tree) required to dismount. Specify this mount point as one of the following:

```
DNFSn:  
DNFSn:[dir.subdir]  
DNFSn:[dir.subdir]file
```

where:

*n*                    Value from 1 to 9999.

[*dir*] or            Directory to mount  
[*dir.subdir*]        (up to eight in addition to the [000000] directory).

*file*                Individual file to dismount.

---

#### Note

---

Type the device name immediately after the keyword DISMOUNT.

---

If you use the /ALL qualifier, you must specify *DNFSn*: without the directory tree.

***logical\_name***

Required (if you omit *mount\_point* and the /ALL qualifier). Default: None.

Logical name that you defined with the MOUNT command of the device to dismount.

**Qualifiers****/ALL**

Optional.

Dismounts one of the following:

- All file systems from all servers: DISMOUNT /ALL
- All file systems on the specified server: DISMOUNT /ALL /HOST=*host*
- All file systems on the specified device: DISMOUNT DNFS*n*: /ALL

If you dismount using the /ALL qualifier, the dismount operation completes even if the server is not currently reachable.

**/HOST=*host***

Optional. Default: None.

Dismounts all file systems from the specified NFS server.

**/WAIT****/NOWAIT**

Optional. Default: /NOWAIT.

- /WAIT
  - Does not dismount the mounted file system if outstanding activities exist.
  - Waits until the dismount has been completed.
  - If you try to access any files on the mount point, the dismount fails.
- /NOWAIT
  - The client completes the command immediately.
  - Dismounting does not actually occur until all file activity has completed.

**Examples**

1. TCPIP> DISMOUNT DNFS3:

Makes the file system mounted on local device DNFS3: inaccessible to local users.

2. TCPIP> DISMOUNT DNFS4:[USR.MNT]

Dismounts only the specified mount point, [USR.MNT], on local device DNFS4:.

3. TCPIP> DISMOUNT DNFS5: /WAIT

Dismounts the DNFS5:[000000] mount point and waits for it to occur.

4. TCPIP> DISMOUNT /ALL

Dismounts all mount points on all devices.

## DISMOUNT

5. TCPIP> DISMOUNT /ALL /HOST="robin"

**Dismounts all mount points served by host robin.**

---

## ENABLE SERVICE

Enables a service on the running TCP/IP Services software.

**Related commands:** DISABLE SERVICE, SHOW SERVICE

### Format

```
ENABLE [NO]SERVICE [ service ]  
                    [ /ADDRESS=IP_address ]  
                    [ /PORT=n ]  
                    [ /PROCESS=process ]  
                    [ /PROTOCOL=protocol ]
```

### Parameters

***service***

Optional. Default: All services.

Specifies the service to enable. The service must be defined in the services database. ENABLE NOSERVICE removes the entry for the service from the list of enabled services.

### Qualifiers

***/ADDRESS=IP\_address***

Optional. Default: 0.0.0.0.

Binds the service only to the specified address. If your host is multihomed, use this qualifier to configure the service to be offered on a specific Internet interface.

***/PORT=n***

Optional. Starts the service on the specified port.

***/PROCESS=process***

Optional.

Runs the service as the specified process.

***/PROTOCOL=protocol***

Optional. Default: TCP.

Runs the service with the specified protocol.

### Examples

1. TCPIP> ENABLE SERVICE TELNET

Initializes TELNET communications.

2. TCPIP> ENABLE SERVICE RLOGIN /ADDRESS=130.180.4.7

Starts the remote login service for users on the host with IP address 130.180.4.7.

## ENABLE SERVICE

3. TCPIP> ENABLE SERVICE SMTP

Starts the SMTP receiver. To start the SMTP sender, see the START MAIL command. For instructions on how to start the SMTP sender when TCP/IP Services starts up, see the SET CONFIGURATION ENABLE SERVICE command.



---

**EXIT**

Exits from the management program.

**Format**

EXIT

## EXPORT

---

## EXPORT

Copies a file from within a container directory to an OpenVMS file.

**Related commands:** IMPORT, DIRECTORY

### Format

```
EXPORT "/path/name" vms_file_name
```

### Restrictions

No wildcards.

### Parameters

***"/path/name"***

Required.

Specifies the container directory and name of the file you want to copy.

***vms\_file\_name***

Required.

Specifies the target OpenVMS file name for the copied file.

### Examples

```
1. TCPIP> EXPORT "/upland/sand/piper" USER1$:[BIRDY]JOBS.TXT
```

Copies the file `piper` from the container directory `/upland/sand` to the regular OpenVMS file `JOBS.TXT` in directory `[BIRDY]` on disk `USER1$:`.

---

**HELP**

Displays online help for using management commands.

**Format**

HELP [ *topic* ]

## IMPORT

---

## IMPORT

Copies an OpenVMS file to a UNIX file located in a container directory.

**Related commands:** EXPORT, DIRECTORY

**Applies to:** NFS server

### Format

```
IMPORT vms_file_name "/path/name"
      [ /[NO]CONVERT ]
      [ /HOST=host ]
      [ /[NO]LOG ]
      [ /MODE=n ]
      [ /UID=n ]
      [ /USER_NAME=vms_user_name ]
```

### Restrictions

No wildcards.

### Parameters

***vms\_file\_name***

Required.

Name of the file to copy.

***"/path/name"***

Required.

Specifies the name of the UNIX container directory into which you want to copy the file and a file name.

### Qualifiers

**/CONVERT**

**/NOCONVERT**

Optional. Default: /CONVERT.

Converts OpenVMS record files to STREAM\_LF files. (The NFS server stores UNIX files in STREAM\_LF format.)

**/HOST=*host***

Optional.

Selects specific hosts if the proxy database has multiple host entries with the same user name and UID.

**/LOG**

**/NOLOG**

Optional. Default: Displays values for host, UID, GID, and user name.

Displays a full description of the specified proxy database record for you to determine ownership.

**/MODE=*n***

Optional. Default: 755 (provides the following protection for owner, group, and world: rwx-rx-rx).

Specifies a UNIX protection mask for a new directory.

Specify octal values in the following order: user, group, others. The values are:

- 0 — No access
- 1 — Execute access
- 2 — Write access
- 3 — Write and execute access
- 4 — Read access
- 5 — Read and execute access
- 6 — Read and write access
- 7 — Read, write, and execute access

For example, /MODE=751 provides:

User	Read, write, and execute access	7	rwx
Group	Read and execute access	5	rx
Other	Execute access	1	x

**/UID=*n***

Optional. Default: Determined with CREATE DIRECTORY.

Selects a specific entry in the proxy database to determine the ownership of the UNIX file.

In the proxy database:

- UID and GID fields identify UNIX ownership.
- User name field identifies OpenVMS ownership.

If you want to access an entry in the proxy database without a unique UID and user name combination, you might need to specify the /HOST qualifier. For example, the same UID and user name combination could appear on multiple hosts.

You can use the /UID qualifier in any combination with the /HOST and /USER\_NAME qualifiers. However, if you do not have SYSPRV or BYPASS privilege, the values you specify must correspond to the values for your user name in the proxy database.

**/USER\_NAME=*vms\_user\_name***

Optional. Default: None.

Selects a specific entry in the proxy database to determine the ownership of the UNIX file.

The UID and GID fields in this entry establish the file's UNIX identity, while the user name field provides the OpenVMS ownership.

If you want to access an entry in the proxy database without a unique UID and user name combination, you might need to specify the /HOST qualifier. For example, the same UID and user name combination could appear on multiple hosts.

## IMPORT

If you have **SYSPRV** or **BYPASS** privilege and do not specify the **/USER\_NAME** qualifier, the proxy record with a **UID** of 0 and a **GID** of 1 is selected.

**SYSPRV** or **BYPASS** privilege is required to select a user name that has a **UIC** different from the **UIC** of the process running the management program.

You can use the **/USER\_NAME** qualifier in any combination with the **/HOST** and **/UID** qualifiers. However, if you do not have **SYSPRV** or **BYPASS** privilege, the values you specify must correspond to the values for your user name in the proxy database.

If you do not specify the **/USER\_NAME** qualifier, the proxy record with a **GID** of 1 and a **UID** of 0 is selected. If there is no proxy entry for the **UID** of 0, **IMPORT** fails.

### Examples

1. `TCPIP> IMPORT USER1$:[BIRDY]JOBS.TXT "/upland/sand/piper"`

**Copies the file JOBS.TXT to the new file piper in the container directory /upland/sand. The file's ownership depends on the directory information specified with the CREATE DIRECTORY command.**

---

## LIST COMMUNICATION\_CONTROLLER

Displays the communication controllers known to the TCP/IP Services software.

**Related commands:** DEFINE COMMUNICATION\_CONTROLLER, DELETE COMMUNICATION\_CONTROLLER

### Format

```
LIST COMMUNICATION_CONTROLLER [ controller ] [ /INTERNET_INTERFACE=character ]
```

### Restrictions

Requires OPER privilege.

### Parameters

***controller***

Optional. Default: All devices.

Displays information about the OpenVMS device specified by *controller*.

Specify the controller name that was used when the device was set up with the DEFINE COMMUNICATION\_CONTROLLER command.

### Qualifiers

**/INTERNET\_INTERFACE=*letter***

Optional. Default: All letters.

Displays entries with the specified *letter*, which represents the first letter of an interface name. See the *Compaq TCP/IP Services for OpenVMS Management guide* for more information.

### Examples

```
1.  TCPIP> LIST COMMUNICATION_CONTROLLER
                                     Communication Controller Configuration
Controller:  LO  Internet Interface:  L
                Description:
                Type:  LOCAL
Controller:  WI  Internet Interface:  W
                Description:
                Type:  WIRELESS
Controller:  EC  Internet Interface:  C
                Description:
                Type:  CLUSTER ETHERNET
Controller:  XE  Internet Interface:  D
                Description:
                Type:  CLUSTER ETHERNET
Controller:  EF  Internet Interface:  F
                Description:
                Type:  CLUSTER ETHERNET
Controller:  CL  Internet Interface:  I
                Description:  ATM Classical IP
                Type:  FDDI
```

## LIST COMMUNICATION\_CONTROLLER

```
Controller: EL  Internet Interface: L
                Description: ATM Emulated LAN
                Type: FDDI
Controller: PP  Internet Interface: P
                Description: Point to Point Protocol
                Type: PPP
Controller: EB  Internet Interface: B
                Description: Shared Memory LAN
                Type: CLUSTER ETHERNET
Controller: EI  Internet Interface: I
                Description: Fast Ethernet - I82558
                Type: CLUSTER ETHERNET
Controller: FA  Internet Interface: A
                Description:
                Type: CLUSTER FDDI
Controller: FC  Internet Interface: C
                Description:
                Type: CLUSTER FDDI
Controller: IC  Internet Interface: C
                Description:
                Type: CLUSTER TOKEN_RING
Controller: IR  Internet Interface: R
                Description:
                Type: CLUSTER TOKEN_RING
Controller: SL  Internet Interface: S
                Description:
                Type: SERIAL
Controller: CL  Internet Interface: I
                Description: ATM Classical IP
                Type: FDDI
```

TCPIP>

**Displays all the information in the table used to match OpenVMS device names with Internet interface names.**



---

## LOOP

Sends ICMP ECHO packets to hosts to determine whether they are active. Same as the PING command.

### Format

```
LOOP [ host ]  
      [ /ADDRESS=xx.xx.xx.xx ]  
      [ /ALL ]  
      [ /FULL ]  
      [ /NUMBER_PACKETS=n ]  
      [ /PACKET_SIZE=n ]  
      [ /PATTERN="hexadecimal-string" ]  
      [ /[NO]ROUTE ]  
      [ /WAIT=n ]
```

### Parameters

#### ***host***

Optional. Default: None.

Specifies the host to which the test packets are sent. Omitting the *host* parameter and the /ADDRESS qualifier tests the TCP/IP Services software on the local node, as defined by the system logical TCPIP\$INET\_HOST.

### Qualifiers

#### **/ADDRESS=*xx.xx.xx.xx***

Optional.

Specifies the IP address of the host to which the test packets are sent.

#### **/ALL**

Optional. Default: Not all requests.

Displays all ICMP ECHO\_REQUESTs, even if not in direct response to this operation.

#### **/FULL**

Optional.

Numeric output only. No attempt is made to look up symbolic names for host addresses. This occurs only when displaying ICMP packets other than ECHO\_RESPONSE.

#### **/NUMBER\_PACKETS=*n***

Optional. Default: 4 packets

Specifies the number of packets to send. If you specify 0, packets are sent continuously until you terminate the LOOP command with Ctrl/C.

#### **/PACKET\_SIZE=*n***

Optional. Default: 64 bytes.

Specifies the size of the ICMP ECHO\_REQUEST.

## LOOP

### **/PATTERN=*hexadecimal-string***

Optional.

Fills out the packet you send with up to 16 bytes, which is useful for diagnosing data-dependent problems. The *hexadecimal-string* is a string of hexadecimal digits of up to 32 characters (16 bytes).

For example, /PATTERN="ff" causes the sent packet to be filled with ones (1).

### **/ROUTE**

### **/NOROUTE**

Optional. Default: /ROUTE.

/ROUTE                    Request is routed through the normal routing tables.

/NOROUTE                Normal routing tables are bypassed.  
If the host is not on the LAN, you get an error.

### **/WAIT=*n***

Optional.

Specifies the number of seconds to wait between sending packets.

## Examples

1. TCP/IP> LOOP thrush  
Tests the connectivity path to UNIX host thrush.
2. TCP/IP> LOOP  
Tests the local TCP/IP Services software.
3. TCP/IP> LOOP /NOROUTE thrush  
Tests the path to the UNIX host thrush without using normal routing tables.

---

## MAP

Maps (logically links) one of the following to the NFS server:

- OpenVMS disk — Requires one execution of MAP to map the disk to a UNIX path name.
- Container file system — Requires two executions of MAP. The first maps the disk, and the second maps the file system.

Mapping creates a logical file system, also called an NFS file system. A logical file system (with an entry in the export database) is accessible to NFS client users for mounting.

To make a file system available on all nodes of a cluster, map it on each node.

Mapping is one step in the tasks necessary to give remote users access to a file system that physically resides on an OpenVMS host running an NFS server:

1. Map the file system.
2. Export the file system (add an entry in the export database).
3. Give potential users entries in the proxy database.

MAP settings are not permanent. To map file systems in the permanent configuration database, issue SET CONFIGURATION [NO]MAP.

**Related commands:** ADD EXPORT, SHOW EXPORT, REMOVE EXPORT, SET CONFIGURATION MAP, SET CONFIGURATION NOMAP, SHOW MAP, SHOW CONFIGURATION MAP, UNMAP

### Format

```
MAP "file system name" logical_file_system
```

### Restrictions

Requires SYSPRV and BYPASS privileges.

### Parameters

**"file system name"**

Required.

Specifies the name for the file system or disk. In the case of mapping a disk, the *"/path"* can be only one level from the root. This parameter specifies the name by which users will access the file system.

**logical\_file\_system**

Required.

Specifies the file system to make known to the NFS server.

To map an OpenVMS file system, specify its disk:

```
MAP "/disk" disk:
```

To map a container file system, specify the disk and the directory name:

```
TCP/IP> MAP
"/container_name" disk:[vms.directory.name]
```

# MAP

## Examples

1. TCPIP> (TCPIP>)MAP "/usr" CANARY\$DUA2:

**Maps local disk CANARY\$DUA2: to /usr. This disk can be exported as /usr to users on remote NFS clients.**

2. TCPIP> MAP "/remote" VERDIN\$DUA3:  
TCPIP> MAP "/flyers" VERDIN\$DUA3:[UNIX\_BIRD\_FILES]

**Maps [UNIX\_BIRD\_FILES], a container file system on disk VERDIN\$DUA3:, to /flyers. This file system can be exported as /flyers to NFS server users. (The first MAP command maps the underlying OpenVMS file system.)**

---

## MOUNT

Makes a physically remote file system accessible to local users.

**Applies to:** NFS client

Mounts a remote directory to local device DNFS*n*. Similar in function to the UNIX `/etc/mount` command, MOUNT gives a file system a UNIX path name. (In format and style, MOUNT resembles the DCL command MOUNT.)

You can mount either OpenVMS or UNIX file systems.

**Related commands:** DISMOUNT, SHOW MOUNT

### Format

```
MOUNT mount_point [ volume_label ] [ logical_name ]
      [ /HOST=host ]
      [ /PATH="path/name" ]
      [ /ACP_PARAMS=options ]
      [ /[NO]ADF=option ]
      [ /AUTOMOUNT[=INACTIVITY:time] ]
      [ /BACKGROUND[=options] ]
      [ /CACHE_TIMEOUT[=options] ]
      [ /[NO]CONVERT ]
      [ /DATA=[options] ]
      [ /FILEIDS[=options] ]
      [ /[NO]FORCE ]
      [ /GID=gid ]
      [ /GROUP ]
      [ /OWNER_UIC=n ]
      [ /PROCESSOR=acp_option ]
      [ /PROTECTION=protections ]
      [ /RETRIES=n ]
      [ /SERVER_TYPE=type ]
      [ /SHARE ]
      [ /[NO]SUPERUSER=uid ]
      [ /SYSTEM ]
      [ /TIMEOUT=OpenVMS_delta_time ]
      [ /UID=uid ]
      [ /USER=user ]
      [ /[NO]WRITE ]
```

### Restrictions and Tips

If you mount remote OpenVMS directories where the NFS server is running TCP/IP Services software, use the /NOADF qualifier on the MOUNT command line unless you are using the OpenVMS-to-OpenVMS integration feature.

The /NOADF requirement applies only if the remote NFS server is running versions of TCP/IP Services earlier than Version 3.3 and cannot participate in OpenVMS-to-OpenVMS mode operation. Other tips include:

- Required order of command keywords: the MOUNT keyword, immediately followed by *mount\_point*. Example: MOUNT DNFS01:
- For the qualifiers that require a time value, specify OpenVMS delta time.

## MOUNT

- Whenever you specify multiple options and values, use the following syntax:  
*/qualifier=(option\_a:value1,option\_b:value2,value3)*

### Parameters

#### ***mount\_point***

Required.

Local device (and optional directory tree) on which to mount the remote NFS file system. Specify this mount point as one of the following:

DNFS*n*:  
DNFS*n*:*[dir.subdir]*  
DNFS*n*:*[dir.subdir]file*

where:

*n* Specifies the unit number. Specify a value from 0 to 9999. Specifying 0 causes the client to choose the next available unit number. (It does not mount a device named DNFS0:.)

*[dir]* or *[dir.subdir]* Specifies the directory to mount (up to eight subdirectories in addition to the [000000] directory).

*file* Specifies the individual file to mount.

---

#### Note

---

Type the device name (*mount\_point*) immediately after the keyword MOUNT.

---

#### ***volume\_label***

Optional. Default: First 12 characters of the combined values of the /HOST and /PATH qualifiers.

Specifies the ODS-2 volume label used for the remote path name.

You can use this qualifier to provide a unique volume label on a system where there is a label conflict. The client does the following:

- Accepts only the first 12 characters for all other entries.
- Applies *volume\_label* only on the first mount of a particular disk.
- Ignores *volume\_label* with subsequent mounts on that disk.

#### ***logical\_name***

Optional. Default: None.

Specifies the logical name associated with the volume.

The client creates the following logical definitions, depending on what you specify:

- If you mount DNFS*n*:*[000000]*, the client defines the logical name as DNFS*n*:

- If you mount `DNFSn:[dir.dir]`, the client defines the logical name as `DNFSn:[dir.dir.]`. The extra dot allows for relative directory specifications. If you issue the following command:

```
$ SET DEFAULT logical:[subdir]
```

The full default definition becomes:

```
DNFSn:[dir.dir.subdir]
```

The client places the logical name in the SYSTEM logical name table, unless you specify the /GROUP or /SHARE qualifier. The client deletes the logical name from the SYSTEM table when you dismount the volume. The process must have SYSNAM privilege to mount a system mount point. Without SYSNAM or GRPNAM privilege, the user must specify /SHARE for a JOB mount. (See the /SHARE qualifier for more information.)

## Qualifiers

### **/ACP\_PARAMS=**

```
{ BUFFER_LIMIT=n | DUMP | IO_DIRECT=n | IO_BUFFERED=n |
MAX_WORKSET=pages | PAGE_FILE=file | PRIORITY=base-priority |
WORKSET=pages }
```

Optional.

Specifies modifiable process parameters for the ancillary control process (ACP).

These parameters are dynamic. The NFS client applies your settings at each first start of an ACP.

For descriptions of these options, see the section on RUN (PROCESS) in the *OpenVMS DCL Dictionary*.

### **/ADF=CREATE**

#### **/NOADF**

Optional. Default: /ADF=CREATE.

If attributes data files (ADFs) exist on the NFS server, the /ADF qualifier lets you use them.

The server uses ADFs to store OpenVMS file attributes. These files appear on the server as `.$ADF$file` files, but you cannot view them directly on the local client system.

The option is:

- CREATE

The client uses and updates the ADFs, and creates ADFs for new files.

/NOADF — No ADFs are created or used.

### **/AUTOMOUNT[=INACTIVITY:*time*]**

Optional. Defaults:

- If you omit this qualifier, automounting is not enabled for this file system.
- If you include the /AUTOMOUNT qualifier but omit the INACTIVITY keyword, file systems are automatically dismounted after five minutes of inactivity.

This qualifier enables automounting for the file system. The file system is automatically mounted when you access its path name.

## MOUNT

You can include the optional **INACTIVITY** keyword to specify the number of minutes of inactivity before automatically dismounting the file system. Be sure to specify the *time* as *hh:mm:ss*. When this inactive period expires, the NFS client dismounts the path name.

**/BACKGROUND [= {DELAY:OpenVMS\_delta\_time | RETRY:n}]**

Optional. Defaults:

- If you omit this qualifier, background mode mounting is not attempted.
- If you omit the **DELAY** keyword, background mode mounting is set up with **/BACKGROUND=(DELAY:00:00:30,RETRY:10)**.

This qualifier enables background mode for mounting the file system.

The optional **DELAY** time specifies amount of time to wait if the mount attempt fails before trying again. Specify the time as *hh:mm:ss*. The maximum delay period you can specify is approximately 49 days. The default delay time is 30 seconds.

The optional **RETRY** keyword specifies the number of times to repeat the attempt to mount the file system. **RETRY:0** means that the client uses the first try only. The default number of times to retry is 10.

If you use the **/BACKGROUND** qualifier, you must also use the **/RETRIES** qualifier and specify a nonzero value. For example:

```
$ TCPIP MOUNT DNFS0: /BACKGROUND=RETRY:9 /RETRIES=4 /HOST="robin" -
_ $ /PATH="/USR/USERS/GEORGE"
```

In this example, you are asking for four data retries on each mount attempt and nine mount attempts, for a total of 36 tries. If you use the default value for **/RETRIES**, the first mount attempt can never complete except by succeeding, and the process doing the mount will hang until the server becomes available.

**/CACHE\_TIMEOUT=**  
[ **DIRECTORY:OpenVMS\_delta\_time** ]  
[ **ATTRIBUTE:OpenVMS\_delta\_time** ]  
[ **READ\_DIRECTORY** ]

Optional. Defaults:

If you omit this qualifier, the file system is set up with caching timeouts as follows:

```
/CACHE_TIMEOUT=(DIRECTORY:00:00:30,ATTRIBUTE:00:00:15)
```

Specifies the following caching timeout information for the mount point:

- **DIRECTORY:OpenVMS\_delta\_time**
  - Amount of time that the client waits between rereading a directory's status or contents.
  - Specify *OpenVMS\_delta\_time* as *hh:mm:ss*.
- **ATTRIBUTE:OpenVMS\_delta\_time**
  - Amount of time that the client waits between rereading a file's attributes from the NFS server.
  - Specify *OpenVMS\_delta\_time* as *hh:mm:ss*.



- READ\_DIRECTORY
  - Forces the client to read the contents of the directory requested when the cache timeout occurs rather than rely on the directory's modified time.
  - By reading the directory contents, the client can be aware of any changes to the number of files within the directory, even if the directory's modify time was not updated.

**/CONVERT****/NOCONVERT**

Optional. Default: /CONVERT.

Converts files with the following attributes to STREAM\_LF files:

- Sequential
- Variable length
- Carriage return/carriage control (VAR-CR)

The convert feature works with some utilities and DCL commands but not with others. For example, it works with the CREATE command and with EDIT/TPU, but it does not work with COPY, BACKUP, or EDIT/EDT. There is no simple way to identify what works. However, for the feature to take effect, the following conditions must be satisfied:

- The file attributes must be sequential, variable length, and carriage return/carriage control.
- The file must be opened for exclusive write access (generally true for newly created files).
- The file must be opened with the FABSM\_SQO bit set in the FAB\$L\_FOP field.
- The file creation and the open for write must be done in one step. That is, if the program first creates the file and afterward opens it for write, the convert feature does not work.

You can convert only those files that were opened using RMS sequential access. For additional information, see the *Compaq TCP/IP Services for OpenVMS Management* manual.

**/DATA [= {read\_bytes | write\_bytes}]**

Optional. Default: /DATA=(8192,8192).

Largest amount of NFS data received or transmitted in one network operation. The options mean:

- *read\_bytes* — Data received. Minimum value = 512.
- *write\_bytes* — Data transmitted. Minimum value = 512.

If you specify only one value, it applies to both READ and WRITE.

You do not need to use /DATA unless a remote NFS server imposes a restriction on data size. If the server requests a smaller transfer size than you specified, the server's requested value overrides the one you set.

**/FILEIDS [= {UNIQUE | NONUNIQUE}]**

Optional. Default: /FILEIDS=UNIQUE.

## MOUNT

With **UNIQUE**, the client uses the file name and 32-bit NFS file ID when processing the directory information returned by the server to determine whether cached information is valid.

With **NONUNIQUE**, the client uses the file handle instead of the file ID. This can refresh directory entries in the client's cache more quickly. However, this can degrade performance because the client must issue additional RPC requests to get the file handle.

### **/FORCE**

### **/NOFORCE**

Optional. Default: **/NOFORCE**.

Performs an overmount or a mount that can cause file system occlusion.

Required privileges:

- **OPER**
- **SYSPRV** (for overmounting a **/SYSTEM** mount)
- **GRPNAM** (for overmounting a **/GROUP** mount)

### **/GID=*n***

Optional. Default: **-2**.

Default GID if no GID mapping exists for file access.

Restriction: Requires **OPER** privilege.

### **/GROUP**

Optional. Default: User mounted.

Adds the logical name to the group logical name table. If the mount is the first one on the volume, **/GROUP** marks the volume as being group-mounted.

Restrictions:

- Requires **GRPNAM** privilege.
- **/GROUP** and **/SYSTEM** are mutually exclusive.

### **/HOST=*host***

Required.

Remote NFS server on which the physical files reside. Type either domain-name or IP-address format.

### **/OWNER\_UIC=*n***

Optional. Default: Ownership recorded on the volume.

UIC-assigned ownership of the volume while you mount it.

Applied only on the first mount of an NFS disk.

### **/PATH="*/path/name*"**

Required.

Path name on the NFS server (specified by **/HOST**). Must match an exported directory, subdirectory, or file of an exported file system on the server.

The */path/name* is mounted as the master file directory (MFD) of the specified device.

**/PROCESSOR= {UNIQUE | SAME:DNFS*n*: | FILE:*file*}**

Optional. Default: New ACP for each mount.

Associates an ancillary control process (ACP) to process the volume, overriding the default manner in which the client associates ACPs with NFS devices (starting a new ACP for each mount request). The options are:

- UNIQUE
  - Creates a new ACP for the new NFS device.
  - Requires OPER privilege.
- SAME:DNFS*n*:
  - Uses the same ACP as the specified device.
  - Requires OPER privilege.
- FILE:*file*
  - Creates a new ACP running the image specified by *file*. Do not use wildcards, host names, or directory names.
  - Requires CMKRNL or OPER privilege.

**/PROTECTION=*protections***

Optional. Default: /PROTECTION=(S:RWED,O:RWED,G:RWED,W:RWED).

Protection code for the volume. If you omit a category, the client denies access to that category of user.

Applied only on the first mount of an NFS device and ignored with subsequent mounts on that device.

Restrictions: Requires OPER privilege.

**/RETRIES=*n***

Optional. Default: /RETRIES=0 (the client retries the request forever or until the server responds).

Maximum number of read or write retries if the NFS server fails to respond.

/RETRIES=0 is a close equivalent to a UNIX hard mount. If you attempt to abort a command or program while it is still retrying the I/O operation on a client device, the process enters RWAST state and remains in that state until the NFS server responds. A process in RWAST state cannot be terminated. If the server does not become available, the only way to remove the process without rebooting the client host is to dismount the client device with the /ALL qualifier.

**/SERVER\_TYPE=*type***

Optional. Default: UNIX.

Operating system of the host running NFS server. The values for *type* are:

- UNIX
- IBM\_VM

If the server is TCP/IP Services Version 3.3 or later, this qualifier is ignored because the client and server always operate in OpenVMS-to-OpenVMS mode.

## MOUNT

### **/SHARE**

Places the logical name in the job logical name table and increments the volume mount count regardless of the number of job mounts. When the job logs out, all job mounts are dismounted, causing the volume mount count to be decremented. See the *Compaq TCP/IP Services for OpenVMS Management* manual for more information.

### **/SUPERUSER=*uid***

#### **/NOSUPERUSER**

Optional. Default: /NOSUPERUSER.

Maps users with SYSPRV, BYPASS, or READALL privileges to the superuser UID. The NFS server must allow superuser access.

The normal superuser UID is 0.

/NOSUPERUSER: No mapping.

### **/SYSTEM**

Optional. Default: System mounted.

Places the logical name in the system logical name table unless you specify the /GROUP or /SHARE qualifier. The client deletes the logical name from the system table when you dismount the volume.

Restrictions:

- Requires SYSNAM privilege.
- The /GROUP, /SYSTEM, and /SHARE qualifiers are mutually exclusive.
- Without SYSNAM or GRPNAM privilege, you must use /SHARE for a job mount.

### **/TIMEOUT=*OpenVMS\_delta\_time***

Optional. Default: ::01 (1 second).

Minimum timeout period for initial remote procedure call (RPC) request retransmissions.

Specify the timeout period as your estimate of the typical round-trip time for RPC requests. For slower-speed links — for example, NFS traffic over SLIP — specify a value that is larger than the default.

**Example:** For a maximum read/write size of 8192 (see the /DATA qualifier) over a 19,200-baud SLIP line, set the absolute minimum timeout value as follows:

```
10240 bytes*8 bits per byte
----- = 4.27 seconds
 19,200 bits per second
```

Here, the 10240 bytes is 8192 data bytes plus the worst-case RPC overhead. Because 4.27 seconds is the absolute minimum, a more realistic value for this link is 15 to 30 seconds to allow for other traffic.

### **/UID=*n***

Optional. Default: -2.

Default UID if no UID mapping exists for file access.

Restriction: Requires OPER privilege.

Both the NFS server and NFS client use the proxy database for access control. Compaq strongly recommends that you provide a proxy with a unique UID for every NFS client user.

If you need to provide universal access to world-readable files, you can use the default UID to avoid creating a proxy for every NFS client user. You should avoid using the default UID if clients require additional file access; otherwise, client users may see unpredictable and confusing results when they try to create files. See the *Compaq TCP/IP Services for OpenVMS Management* manual for a detailed discussion about using proxies, the default user, and security considerations.

**/USER=user**

Optional. Default: USER account.

Existing OpenVMS account to which the NFS client maps unknown UIDs.

If the client does not find the USER account, the DECnet account becomes the default. If the client does not find the DECnet account, [200,200] becomes the default.

**/WRITE**

**/NOWRITE**

Optional. Default: /WRITE.

Mounts files with WRITE privilege.

/NOWRITE mounts files as read only.

## Examples

1. TCPIP> MOUNT DNFS2: /HOST="loon" /PATH="/usr/users/curlew"

Mounts, on local device DNFS2:, the remote directory /usr/users/curlew, which resides on NFS server loon.

2. TCPIP> MOUNT DNFS3: /HOST="sigma" -  
\_TCPIP> /PATH="/usr" /AUTO=(INACT:00:10:00)

Using automounting, this command mounts the /usr file system from sigma onto the OpenVMS mount point when it references the path name. The client keeps the path mounted for an inactive period of 10 minutes, after which it dismounts the path name.

3. TCPIP> MOUNT DNFS4: /HOST="sigma" /PATH="/usr" -  
\_TCPIP> /BACKGROUND=(DEL:00:01:00,RET:20) /RETRIES=4

Attempts to mount the /usr file system. If it cannot, it waits 1 minute and retries the connection up to 20 times.

4. TCPIP> MOUNT DNFS5:[USERS.MNT] /HOST="sigma" /PATH="/usr"  
%DNFSMOUNT-S-MOUNTED, /usr mounted on \_DNFS5:[USERS.MNT]  
TCPIP> MOUNT DNFS5:[USERS.MNT] /HOST="sigma" /PATH="/usr/users" /FORCE  
%DNFSMOUNT-S-REMOUNTED, \_DNFS5:[USERS.MNT] remounted as /usr/users on SIGMA

Specifies a lower level in the NFS server path with the second mount. This constitutes another path name and qualifies for an overmount.

## MOUNT

5. TCPIP> MOUNT DNFS22:[USERS.SMITH.MNT] /HOST="sigma" /PATH="/usr"  
%DNFSMOUNT-S-MOUNTED, /usr mounted on \_DNFS22:[USERS.SMITH.MNT]  
  
TCPIP> MOUNT DNFS22:[USERS.SMITH] /HOST="sigma" /PATH="/usr" /FORCE  
%DNFSMOUNT-S-MOUNTED, /usr mounted on \_DFS22:[USERS.SMITH]  
%TCPIP-I-OCCLUDED, previous contents of \_DNFS22:[USERS.SMITH] occluded

**The /FORCE qualifier performs an occluded mount. If you issue the DIRECTORY command, the NFS client occludes (hides from view) the subdirectory dropped from the first MOUNT command.**

**To make the directory visible again, either issue the SHOW MOUNT command (both mounts will be visible) or dismount DNFS22:[USERS.SMITH].**

---

## PING

Sends ICMP ECHO packets to hosts to determine whether they are active. Same as the LOOP command.

### Format

```
PING [ host ]  
      [ /ADDRESS=xx.xx.xx.xx ]  
      [ /ALL ]  
      [ /FULL ]  
      [ /NUMBER_PACKETS=n ]  
      [ /PACKET_SIZE=n ]  
      [ /PATTERN="hexadecimal-string" ]  
      [ /[NO]ROUTE ]  
      [ /WAIT=n ]
```

### Parameters

#### ***host***

Specifies the host to which the test packets are sent.

Omitting *host* tests the TCP/IP Services software on the local node, as defined by the system logical TCPIP\$INET\_HOST.

### Qualifiers

#### **/ADDRESS=*xx.xx.xx.xx***

Optional.

Specifies the IP address of the host to which the test packets are sent.

#### **/ALL**

Optional. Default: Not all requests.

Displays all ICMP ECHO\_REQUESTs, even if not in direct response to this operation.

#### **/FULL**

Optional.

Numeric output only. No attempt is made to look up symbolic names for host addresses. This occurs only when displaying ICMP packets other than ECHO\_RESPONSE.

#### **/NUMBER\_PACKETS=*n***

Optional. Default: 4 packets

Specifies the number of packets to send. If you specify 0, packets are sent continuously until you terminate it with Ctrl/C.

#### **/PACKET\_SIZE=*n***

Optional. Default: 64 bytes.

Specifies the size of the ICMP ECHO\_REQUEST.

#### **/PATTERN="*hexadecimal-string*"**

Optional.

## PING

Fills out the packet you send with up to 16 bytes, which is useful for diagnosing data-dependent problems. The string is a hexadecimal string of up to 32 characters (16 bytes).

For example, /PATTERN="ff" causes the sent packet to be filled with ones (1).

**/ROUTE**

**/NOROUTE**

Optional. Default: /ROUTE.

/ROUTE            Request is routed through the normal routing tables.

/NOROUTE        Normal routing tables are bypassed.  
                  If the host is not on the LAN, you get an error.

**/WAIT=*n***

Optional.

Specifies the number of seconds to wait between sending packets.

### Examples

1. TCP/IP> PING dented

                  Specifies that the local host test the connectivity path to host dented.



---

## REMOVE DIRECTORY

Removes a link to a directory within a UNIX container directory. If there are no other links to it, the directory is deleted.

**Related commands:** CREATE DIRECTORY, DIRECTORY

**Applies to:** NFS server

### Format

```
REMOVE DIRECTORY "/path/name"
```

### Restrictions

Requires:

- Read and write access to the parent directory
- BYPASS privilege

### Parameters

*"/path/name"*

Required.

Directory with the link you want to remove.

### Examples

```
1. TCPIP> REMOVE DIRECTORY "/eagles/eaglet"
```

Removes a link to the directory /eagles/eaglet.

## REMOVE EXPORT

---

## REMOVE EXPORT

Deletes directory names from the export database so that they are not available for mounting by an NFS client.

**Related commands:** ADD EXPORT, SHOW EXPORT, MAP, SET CONFIGURATION MAP, SET CONFIGURATION NOMAP, SHOW MAP, SHOW CONFIGURATION MAP

**Applies to:** NFS server

### Format

```
REMOVE EXPORT "/path/name"
               [ /[NO]CONFIRM ]
               [ /HOST=host ]
```

### Restrictions

Requires read and write access to the export database.

### Parameters

***"/path/name"***

Required.

Directory name to delete from the export database.

### Qualifiers

***/CONFIRM***

***/NOCONFIRM***

Optional. Default: */CONFIRM* if you use a wildcard.

When the software encounters a match, it displays a description and solution and then requests confirmation before deleting each record. Enter one of the following:

- Y to delete the record
- N to save the record

***/HOST=host***

Optional. Default: */HOST=\* (all hosts)*.

Host, running NFS client, that will become unable to access the specified container directory.

Format for multiple hosts:

```
/HOST=("host0","host1","host2")
```

### Examples

```
1. TCPIP> REMOVE EXPORT "/house/finch"
```

Removes the name of container directory */house/finch* from the export database. This directory is now inaccessible to NFS client users.

## REMOVE EXPORT

2. `TCP/IP> REMOVE EXPORT "/oceans/swamps" /HOST=("tern","crane")`

**Modifies the accessibility of local UNIX directory /oceans/swamps. This directory is now unavailable to users working on hosts tern and crane, which run NFS client software.**

## REMOVE FILE

---

### REMOVE FILE

Removes a link to a file within a container directory. If there are no other links to it, the file is deleted.

**Related commands:** DIRECTORY, REMOVE DIRECTORY

**Applies to:** NFS server

#### Format

```
REMOVE FILE "/path/name"
```

#### Restrictions

Requires:

- Read and write access to the parent directory
- BYPASS privilege

#### Parameters

*"/path/name"*

Required.

File with the link you want to remove.

#### Examples

1. TCPIP> REMOVE FILE *"/peacock/feather.care/preening"*  
Removes the NFS link to the file preening.

---

## REMOVE MAIL

Deletes mail messages from SMTP queues.

Without the *user* parameter, all messages from the user name that correspond to your process's user name are deleted.

**Related commands:** SEND MAIL, SHOW MAIL

**Applies to:** SMTP

### Format

```
REMOVE MAIL [ user ]
             [ /[NO]COPY=[directory] ]
             [ /[NO]CONFIRM ]
             [ /ENTRY=n ]
```

### Restrictions

Requires SYSPRV or BYPASS privilege for mail messages that are not yours.

### Parameters

***user***

Optional. Default: All mail messages with your process's user name.

Removes messages sent from the specified user name.

### Qualifiers

**/COPY=[*directory*]**

**/NOCOPY=[*directory*]**

Optional. Default: Messages copied to the user's default directory.

Copies messages to be deleted to the specified directory.

/NOCOPY: Messages are not copied.

**/CONFIRM**

**/NOCONFIRM**

Optional. Defaults:

- With an entry number specified — /NOCONFIRM
- Without an entry number specified — /CONFIRM

If you omit an entry number, requests confirmation before deleting each message.

Enter:

- Y to delete the mail message
- N to save the mail message
- G to change to NO CONFIRMATION mode

**/ENTRY=*n***

Optional. Default: All.

Queue entry numbers to remove from the SMTP queue.

## REMOVE MAIL

### Examples

1. TCPIP> REMOVE MAIL

Removes all messages for your process's user name, or deletes everything in the SMTP queue if you have either SYSPRV or BYPASS privilege.

2. TCPIP> REMOVE MAIL /ENTRY=781

Removes message 781, if it corresponds to your process's user name, or if you have either SYSPRV or BYPASS privilege.

3. TCPIP> REMOVE MAIL BROOD

Removes all messages for BROOD, if your process's user name is BROOD, or if you have either SYSPRV or BYPASS privilege.

4. TCPIP> REMOVE MAIL /USER\_NAME=COCKATOO /COPY=[COCKATOO.OLD\_MAIL]

Removes all messages for COCKATOO, if this is your process's user name, or if you have either SYSPRV or BYPASS privilege. Before deletion, copies this queued mail to the specified directory.

---

## REMOVE PROXY

Deletes entries from the volatile and permanent proxy database.

**Related commands:** ADD PROXY, SHOW PROXY

**Applies to:** NFS server, NFS client, PC-NFS, remote shell, LPR/LPD, and customer-developed services

### Format

```
REMOVE PROXY [ user_name ]
              [ /COMMUNICATION ]
              [ /[NO]CONFIRM ]
              [ /GID=n ]
              [ /HOST=host ]
              [ /NFS=options ]
              [ /PERMANENT ]
              [ /REMOTE_USER=user ]
              [ /UID=n ]
```

### Restrictions

Requires:

- Read and write access to the proxy database
- One of the following privileges:
  - SYSPRV
  - SYSLCK
  - OPER

### Parameters

***user\_name***

Optional. Default: All entries (REMOVE PROXY \*).

Deletes the specified entries from the proxy database.

### Qualifiers

**/COMMUNICATION**

Optional. Default: Both communication and NFS entries.

Deletes communication (non-NFS) proxies.

**/CONFIRM**

**NOCONFIRM**

Optional. Default: /CONFIRM with wildcards.

Requests confirmation before deleting records. Enter one of the following:

- Y to delete the record
- N to save the record
- G to change to NO CONFIRMATION mode

## REMOVE PROXY

### **/GID=*n***

Optional. Default: All GIDs.

Deletes only proxies for the specified group identifier (GID).

### **/HOST=*host***

Optional. Default: All hosts.

Deletes only proxies for the specified host.

### **/NFS=INCOMING**

### **/NFS=OUTGOING**

Optional. Default: /NFS=(INCOMING,OUTGOING).

Deletes an NFS proxy. Specify one of the following:

/NFS=OUTGOING                      Proxy to use NFS client

/NFS=INCOMING                      Proxy to use NFS server

/NFS=(OUTGOING,INCOMING)      Proxy to use NFS client and NFS server

### **/PERMANENT**

Optional. Default: None.

Deletes entries only from the permanent proxy database.

### **/REMOTE\_USER=*user***

Optional. Default: None.

Deletes entries for the specified remote user name.

### **/UID=*n***

Optional. Default: All UIDs.

Limits the search of entries to delete to proxies for the specified UID.

## Examples

1. `TCPIP> REMOVE PROXY "peacock" /HOST=GOLDEN /UID=83`  
Removes authorization for UID 83 on host GOLDEN from OpenVMS account peacock.
2. `TCPIP> REMOVE PROXY /HOST=GOLDEN /UID=83`  
Removes authorization for UID 83 from host GOLDEN.
3. `TCPIP> REMOVE PROXY /HOST=("goose","grouse")`  
Removes authorization for all users on hosts goose and grouse.
4. `TCPIP> REMOVE PROXY /UID=83`  
Totally removes authorization for UID 83.
5. `TCPIP> REMOVE PROXY VMS_USER /REMOTE=PARTRIDGE /HOST=*`  
Removes authorization for remote user PARTRIDGE on all hosts.



---

## SEND MAIL

Requeues a mail message for delivery. Releases jobs that are in a hold state.

**Related commands:** REMOVE MAIL, SHOW MAIL

**Applies to:** SMTP

### Format

```
SEND MAIL [ user ]  
          [ /AFTER=time ]  
          [ /[NO]CONFIRM ]  
          [ /ENTRY=n ]
```

### Restrictions

SYSPRV or BYPASS privilege required to requeue mail messages that do not correspond to your process's user name.

### Parameters

*user*

Optional. Default: All.

Requeues messages sent from the specified user name.

### Qualifiers

**/AFTER=*time***

Optional. Default: Immediate delivery attempt.

Time after which delivery is to be attempted.

**/CONFIRM**

**/NOCONFIRM**

Optional. Defaults:

- With an entry number specified — /NOCONFIRM
- Without an entry number specified — /CONFIRM

Requests confirmation before deleting each message when you omit an entry number. Enter one of the following:

- Y to delete the message
- N to save the message
- G to change to NO CONFIRMATION mode

**/ENTRY=*n***

Optional.

Queue number of the mail message to be re-queued for delivery.

## SET ARP

---

## SET ARP

Maps between an IP address and either an Ethernet or a FDDI address. SET NOARP removes an address-mapping pair.

**Related command:** SHOW ARP

### Formats

```
SET ARP mac_address
      [ host_name | IP_address ]
      [ [/[NO]PERMANENT ]
      [ /[NO]PUBLIC ]

SET NOARP [ host_name|IP_address]
```

### Restrictions

Requires OPER privilege.

### Parameters

***mac\_address***

Required.

Specifies the physical Ethernet or FDDI address to be mapped to an IP address. Not valid with SET NOARP.

***host\_name***

Optional.

Specifies the host on which the targeted interface resides. If you do not supply a host name, you must supply its IP address.

***IP\_address***

Optional.

Specifies the 32-bit address that identifies the network and host. If you do not specify the host's IP address, you must specify its host name.

You cannot use wildcards.

### Qualifiers

**/PERMANENT**

**/NOPERMANENT**

Optional. Default: /PERMANENT.

Specifies whether the mapping information is cached.

/NOPERMANENT removes ARP mapping after the caching interval.

Not valid with SET NOARP.

**/PUBLIC**

**/NOPUBLIC**

Optional. Default: /PUBLIC.

Specifies whether the local ARP responds to ARP requests from other hosts to the specified host.

/NOPUBLIC maps only for the local host.  
Not valid with SET NOARP.

**Examples**

1. TCPIP> SET ARP AA-BB-04-05-06-07 CONDOR

Permanently maps CONDOR's host name to FDDI address  
AA-BB-04-05-06-07.

## SET BOOTP

---

## SET BOOTP

Creates client entries in the BOOTP database.

SET NOBOOTP does not require any qualifiers.

**Related commands:** CONVERT/VMS BOOTP, SHOW BOOTP

### Format

```
SET [NO]BOOTP host
[ /FILE=file]
/HARDWARE=ADDRESS=hex_address
[ /GATEWAYS=hosts ]
[ /NETWORK_MASK=IP_address ]
[ /SERVERS=type=host ]
[ /TIME_OFFSET=seconds ]
```

### Restrictions

Requires read, write, and delete access to the BOOTP database.

### Parameters

***host***

Required.

Specifies the client to which your system will download files upon request. Enter a host name or IP address.

### Qualifiers

***/FILE=file***

Optional.

Specifies the name of the client's system image or other file to download upon request.

- By default, upon receiving a request, BOOTP looks for this file in TCP/IP\$TFTP\_ROOT:[*host*], where *host* is the client's host name, excluding the domain.
- If this directory does not exist, BOOTP uses:  
TCP/IP\$TFTP\_ROOT:[000000].
- When the TCP/IP Services software receives a boot request, BOOTP verifies the existence and size of this file.

***/GATEWAYS=hosts***

***/NOGATEWAYS=hosts***

Optional. Default: None.

Specifies the gateways used for routing.

***/HARDWARE=ADDRESS=hex\_addr***

Required.

Specifies the client's hardware address. For *hex\_addr*, specify: *hh-hh-hh-hh-hh-hh*.

**/NETWORK\_MASK=IP\_address**

Required if you use subnets; otherwise optional.

Specifies the part of the host field of an IP address identified as the subnet.

The software calculates the default by setting the following:

- The bits representing the network field to 1
- The bits representing the host field to 0

You can divide the host field into a site-specific subnetwork and a host field. If you use subnets, you must specify a subnet field.

**/SERVERS=type=host**

Optional.

Specifies other servers whose names BOOTP can supply to clients. Here, *host* specifies a host name or IP address and *type* can be one or more of the following:

[NO]COOKIE	Cookie server
[NO]IEN_NAME	IEN-116 name server
[NO]IMPRESS	Impress network image server (IMAGEN)
[NO]LPR	Berkeley 4BSD print server
[NO]LOG	MIT-LCS UDP logging server
[NO]NAME	BIND name server
[NO]RESOURCE	Resource Location Protocol (RLP) server (RFC-887)
[NO]TIME	Internet time server (RFC-868)

**/TIME\_OFFSET=seconds**

Optional. Default: 0 seconds.

Specifies the time difference, in seconds, between the client's time zone and Universal Coordinated Time (UTC) expressed in seconds. This value is zero (0) in the British Isles and parts of Europe, a positive number for locations east of the zero meridian, and a negative number for locations west of the zero meridian.

## Examples

1. TCPIP> SET BOOTP PLOVER /HARDWARE=ADDRESS=08-00-2D-20-23-21 -  
\_TCPIP> /FILE=PLOVER.SYS

Adds client host PLOVER, with hardware address 08-00-2D-20-23-21 to the BOOTP database. BOOTP can respond to a remote boot request from client PLOVER with a reply packet containing the name of the file to download and its IP address.

2. TCPIP> SET BOOTP ERN /HARDWARE=ADDRESS=98-00-2D-20-23-21 -  
\_TCPIP> /SERVERS=COOKIE=(PLOVER,GULL)

Adds client host ERN to the BOOTP database and specifies that ERN will use PLOVER AND GULL as cookie servers.

3. TCPIP> SET BOOTP PLOVER /HARDWARE=ADDRESS=08-00-2D-20-23-21 -  
\_TCPIP> /SERVERS=(COOKIE=GULL,NAME=BIRDS)

Adds client host PLOVER to the BOOTP database and specifies that PLOVER will use GULL as a COOKIE server and BIRDS as its name server.

## SET COMMUNICATION

---

### SET COMMUNICATION

Modifies the IP, TCP, UDP, and INET\_ACP software on the running system.

**Related commands:** SET CONFIGURATION COMMUNICATION, SHOW COMMUNICATION

#### Format

```
SET COMMUNICATION [ /ACCEPT=options ]  
                  [ /CLUSTER_TIMER=minutes ]  
                  [ /DOMAIN=domain ]  
                  [ /LOCAL_HOST=host ]  
                  [ /PROXIES=n ]  
                  [ /REJECT=options ]
```

#### Restrictions

Requires OPER privilege.

#### Qualifiers

**/ACCEPT { =[NO]HOSTS=(*hosts*) | =[NO]NETWORKS=(*networks*) }**

Optional. Default: All hosts and all networks.

Accepts communication from the hosts and networks specified.

Do not specify the same hosts or networks for both /ACCEPT and /REJECT.

To delete an /ACCEPT entry, specify it again using the NOHOSTS or NONETWORKS option.

Specify one of the following:

- **[NO]HOSTS=*hosts***

Hosts that can access TCP/IP Services. Maximum is 32. For example:

```
/ACCEPT=HOSTS=(host1_name,host2_name, host3_address)
```

- **[NO]NETWORKS=*networks***

Networks that can access TCP/IP Services. Maximum is 16.

Use the following syntax:

```
NETWORKS=(net1[:net1mask],net2[:net2mask],...)
```

For each network, specify: *network:[network\_mask]*. The network mask is optional. (Default: class number of your network. For example, the default for 11.200.0.0. is 255.0.0.0.). For example:

```
/ACCEPT=NETWORKS=(net1_name,net2_addr,net3_addr.net3_mask)
```

**/CLUSTER\_TIMER=*n***

Optional. Default: 5 minutes. (If set to 0, the host holds the cluster host name until you either stop TCP/IP Services or delete the interface.)

Specifies the maximum time given for a node to respond to the cluster name.

**/DOMAIN=*domain***

Optional.

Specifies your system's local domain. This qualifier requires either SYSPRV or BYPASS privilege.

### **/LOCAL\_HOST=*host***

Optional.

Defines the following logical names for the local host:

- **TCPIP\$INET\_HOST=*host-name***  
This logical is always set with the primary host name even if the alias name was specified as *host*.
- **TCPIP\$INET\_HOSTADDR=*host-IP-address***  
If the local host has multiple IP addresses, this logical name is set with a name for each address, called **TCPIP\$INET\_HOSTADDR $n$** , where  $n$  is a number starting at 2.

This qualifier requires either SYSPRV or BYPASS privilege.

### **/PROXIES= $n$**

Optional. Default: Number of communication proxies plus 10, with a minimum of 20.

Specifies the maximum size of the proxy cache. If you plan to add entries to the proxy database after you start the TCP/IP Services software, set /PROXIES to a value higher than the default.

You cannot change this value if the TCP/IP Services software is running.

### **/REJECT {=[NO]HOSTS=(*hosts*) | =[NO]NETWORKS=(*networks*) | =[NO]MESSAGE=(*message*) }**

Optional. Default: No rejections.

Specifies the hosts or networks that cannot access the TCP/IP Services software, including the rejection message that TCP/IP might return.

(For remote login, remote shell, and remote executive, the rejection message is preceded by a byte with a value of 1 and terminated by a byte with a value of zero.)

Do not specify the same hosts or networks for both /ACCEPT and /REJECT.

To delete a /REJECT entry, specify it again using the NOHOSTS or NONETWORKS option.

Specify one of the following:

- **[NO]HOSTS=*hosts*** to list hosts that cannot access TCP/IP Services. Maximum is 32. The syntax is:  
**/REJECT=HOSTS=(*host1\_name,host2\_name,host3\_address*)**
- **[NO]NETWORKS=*networks*** to list networks that cannot access TCP/IP Services. Maximum is 16. The syntax is:

**NETWORKS=(*net1[:net1mask],net2[:net2mask],...* )**

For each network, specify *network.network\_mask*. The network mask is optional. Default: Class number of your network. For example, the default for 11.200.0.0. is 255.0.0.0. The syntax is:

**/REJECT=NETWORKS=(*net1\_name,net2\_address,net3\_addr.net3\_mask*)**

## SET COMMUNICATION

### Examples

1. TCPIP> SET COMMUNICATION -  
\_TCPIP /REJECT=NETWORK=(16.30.0.0:255.255.0.0,16.40.0.0:255.255.0.0)

Sets all the services to inaccessible to the two specified networks.



---

## SET CONFIGURATION BIND

Configures the BIND name server. Creates the BIND server configuration file, which holds the following information:

- Cluster alias or aliases
- Server type (primary, secondary, or forwarding)
- Domains to be served
- Location from which the BIND server gets initial information for lookups

You can configure the BIND server as follows:

- For one or more internet domains
- As one kind of BIND server (primary, secondary, or forwarding)
- As multiple kinds of BIND servers
- On TCP/IP clusters for cluster load balancing

This command does not create a BIND 8.1 configuration. If you want to take full advantage of the new features available with the BIND 8.1 implementation, you should set up your BIND environment by editing the TCPIP\$BIND.CONF configuration file. See the *Compaq TCP/IP Services for OpenVMS Management* manual for detailed instructions.

If you choose to configure your BIND environment with the SET CONFIGURATION BIND command, you must enter the command CONVERT/CONFIGURATION BIND before running BIND.

**Related commands:** SHOW CONFIGURATION BIND, CONVERT /CONFIGURATION BIND

### Format

```
SET CONFIGURATION [NO]BIND [ /CACHE=options ]
                        [ /[NO]CLUSTER=names ]
                        [ /FORWARDERS=options ]
                        [ /PRIMARY=options ]
                        [ /SECONDARY=options ]
```

### Restrictions

Requires SYSPRV or BYPASS privilege.

### Qualifiers

**/CACHE=([NO]DOMAIN:*do*,[NO]FILE:*file*)**

Optional. Default: None.

Specifies the cache server for the specified domain. Do not use with /FORWARDERS. Use with /PRIMARY and /SECONDARY.

The cache tells the primary or secondary server how to use hints to find the file. These hints let a server find a root name server. With this ability, the server can answer requests even if it does not have the information. You can use the following options:

- DOMAIN keys to a particular record within a type.

## SET CONFIGURATION BIND

NODOMAIN deletes the entry.

- FILE specifies the name of the hints file.

If you use /CACHE with no options:

- DOMAIN defaults to "." ("root").
- FILE defaults to NAMED.CA.

**/CLUSTER=*name***

**/NOCLUSTER=*name***

Required to configure cluster load balancing.

Identifies the name of a TCP/IP cluster as the first step to setting up cluster load balancing.

For information about the remaining procedure, see the *Compaq TCP/IP Services for OpenVMS Management* manual.

**/NOCLUSTER=*name*** deletes the specified name as a cluster load-balancing host.

**/FORWARDERS=(*[NO]HOST:host*)**

Optional.

Specifies the forwarding server.

NOHOST deletes hosts.

**/PRIMARY=(*[NO]DOMAIN:do,[NO]FILE:file*)**

Optional. Default: None.

Specifies the primary server for the specified zone. Multiple primary servers are allowed if each is associated with a different domain.

- DOMAIN keys to a particular domain.

NODOMAIN deletes the entry.

- FILE specifies the domain to be served.

If you do not specify a file, the default file name is created from the value that you supply with the DOMAIN option.

NOFILE specifies that no file is created.

**/SECONDARY=(*[NO]DOMAIN:do,[NO]FILE:file,[NO]HOST:host*)**

Optional. Default: None.

Specifies the secondary server for the specified zone. Multiple secondary servers are allowed if each is associated with a different domain.

- DOMAIN keys to a particular record within a type.

NODOMAIN deletes the entry.

- FILE specifies the name of the boot file.

If you do not specify a file, the default file name is created from the value that you supply with the DOMAIN option.

NOFILE specifies that no file is created.

- HOST is a list of hosts from which the secondary server copies the database file.

NOHOST deletes hosts from the host list.

### Examples

1. TCPIP> SET CONFIGURATION BIND -  
\_TCPIP> /PRIMARY=(DOMAIN:RHEA.LAB.UBIRD.EDU)

**Configures the host as the primary server for domain RHEA.LAB.UBIRD.EDU.**

2. TCPIP> SET CONFIGURATION BIND -  
\_TCPIP> /SECONDARY=(DOMAIN:JACANA.LAB.UBIRD.EDU) -  
\_TCPIP> /SECONDARY=(FILE:JACANA.DB,HOST=MARSHY)

**Configures the host as a secondary server for domain JACANA.LAB.UBIRD.EDU and names the boot file JACANA.DB.**

**Omitting the file name would default to file JACANA\_LAB\_UBIRD\_EDU.DB.**

3. TCPIP> SET CONFIGURATION BIND -  
\_TCPIP> /SECONDARY=(DOMAIN:0.192.IN-ADDR.ARPA,HOST:WEBBED)

**Configures the host as a secondary server for the reverse lookup domain for addresses that have the form 192.0.\*.\*.**

**The boot file name defaults to 0\_192\_IN-ADDR\_ARPA.DB and the host copies this file from the host WEBBED.**

4. TCPIP> SET CONFIGURATION BIND /CACHE

**Points the server to the cache file (NAMED.CA), which contains hints about the root name servers.**

## SET CONFIGURATION COMMUNICATION

---

### SET CONFIGURATION COMMUNICATION

Enters information into the configuration database to start the IP, TCP, UDP, and INET\_ACP software when the system starts up.

When TCP/IP Services starts up, this configuration overrides the default settings.

**Related commands:** SHOW CONFIGURATION COMMUNICATION, SET COMMUNICATION

#### Format

```
SET CONFIGURATION COMMUNICATION [ /ACCEPT=options ]  
                                [ /CLUSTER_TIMER=minutes ]  
                                [ /DOMAIN=domain ]  
                                [ /LOCAL_HOST=host ]  
                                [ /PROXIES=n ]  
                                [ /REJECT=options ]
```

#### Restrictions

Requires OPER privilege.

#### Qualifiers

**/ACCEPT { =[NO]HOSTS=(*hosts*) | =[NO]NETWORKS=(*networks*) }**

Optional. Default: All hosts and all networks.

Accepts communication from the hosts and networks specified.

Do not specify the same hosts or networks for both /ACCEPT and /REJECT.

To delete an /ACCEPT entry, specify it again using the NOHOSTS or NONETWORKS option.

Specify one of the following:

- **[NO]HOSTS=*hosts***

Hosts that can access TCP/IP Services. Maximum is 32. For example:

```
/ACCEPT=HOSTS=(host1_name,host2_name,host3_address)
```

- **[NO]NETWORKS=*networks***

Networks that can access TCP/IP Services. Maximum is 16.

The syntax is:

```
NETWORKS=(net1[:net1mask],net2[:net2mask],...)
```

For each network, specify: *network:[network\_mask]*. The network mask is optional. (Default: class number of your network. For example, the default for 11.200.0.0. is 255.0.0.0.). For example:

```
/ACCEPT=NETWORKS=(net1_name,net2_addr,net3_addr.net3_mask)
```

**/CLUSTER\_TIMER=*n***

Optional. Default: 5 minutes. (If set to 0, the host holds the cluster host name until you either stop TCP/IP Services or delete the interface.)

Specifies the maximum time given for a node to respond to the cluster name.

## SET CONFIGURATION COMMUNICATION

### **/DOMAIN=*domain***

Optional.

Specifies your system's local domain. This qualifier requires either SYSPRV or BYPASS privilege.

### **/LOCAL\_HOST=*host***

Optional.

Defines the following logical names for the local host:

- **TCPIP\$INET\_HOST=*host-name***  
This logical is always set with the primary host name, even if the alias name was specified as host.
- **TCPIP\$INET\_HOSTADDR=*host-IP-address***  
If the local host has multiple IP addresses, this logical name is set with a name for each address, called TCPIP\$INET\_HOSTADDR*n*, where *n* is a number starting at 2.

This qualifier requires either SYSPRV or BYPASS privilege.

### **/PROXIES=*n***

Optional. Default: Number of communication proxies plus 10, with a minimum of 20.

Specifies the maximum size of the proxy cache. If you plan to add entries to the proxy database after you start the TCP/IP Services software, set /PROXIES to a value higher than the default.

You cannot change this value if the TCP/IP Services software is running.

### **/REJECT { =[NO]HOSTS=(*hosts*) | =[NO]NETWORKS=(*networks*) | =[NO]MESSAGE=(*message*) }**

Optional. Default: No rejections.

Specifies the hosts or networks that cannot access the TCP/IP Services software, including the rejection message that TCP/IP might return.

(For remote login, remote shell, and remote executive, the rejection message is preceded by a byte with a value of 1 and terminated by a byte with a value of 0.)

Do not specify the same hosts or networks for both /ACCEPT and /REJECT.

To delete a /REJECT entry, specify it again using the NOHOSTS or NONETWORKS option.

Specify one of the following:

- **[NO]HOSTS=*hosts*** to list hosts that cannot access TCP/IP Services. Maximum is 32. The syntax is:  
**/REJECT=HOSTS=(*host1\_name,host2\_name, host3\_address*)**
- **[NO]NETWORKS=*networks*** to list networks that cannot access TCP/IP Services. Maximum is 16. The syntax is:  
**NETWORKS=(*net1[:net1mask],net2[:net2mask],...* )**

For each network, specify *network.network\_mask*. The network mask is optional. Default: Class number of your network. For example, the default for 11.200.0.0. is 255.0.0.0. The syntax is:

## SET CONFIGURATION COMMUNICATION

*/REJECT=NETWORKS=(net1\_name,net2\_address,net3\_addr.net3\_mask)*

### Examples

1. TCPIP> SET CONFIGURATION COMMUNICATION -  
\_TCPIP /REJECT=NETWORK=(16.30.0.0:255.255.0.0,16.40.0.0:255.255.0.0)

**In the configuration database, sets all the services to inaccessible to the two specified networks.**

---

## SET CONFIGURATION ENABLE SERVICE

Starts specified services when TCP/IP Services starts up. This command modifies the permanent configuration database.

SET CONFIGURATION ENABLE NOSERVICE removes the entry for the service from the list of enabled services in the configuration database.

**Related commands:** SHOW CONFIGURATION ENABLE SERVICE, ENABLE SERVICE

### Format

```
SET CONFIGURATION ENABLE [NO]SERVICE [ service ]
```

### Parameters

**service**  
Required.

Specifies the service to configure to start up.

### Qualifiers

**/COMMON**  
Optional. Default: Node specific.

Enters information in the configuration database for the clusterwide enabling or disabling of services.

### Examples

1. TCPIP> SET CONFIGURATION ENABLE SERVICE TELNET

In the configuration database, initializes TELNET communications.

2. TCPIP> SET CONFIGURATION ENABLE SERVICE RLOGIN

In the configuration database, starts the remote login service.

3. TCPIP> SET CONFIGURATION ENABLE SERVICE SMTP

In the configuration database, enables the SMTP receiver.

For more information about starting SMTP, see the *Compaq TCP/IP Services for OpenVMS Management* guide.

## SET CONFIGURATION INTERFACE

---

### SET CONFIGURATION INTERFACE

Enters information into the configuration database, which defines one of the following when TCP/IP Services starts up:

- An Internet interface (hardware connection to the network)
- A serial line Internet interface (a form of hardware connection to the network)
- A pseudointerface (a data structure that extends subnet routing so that, on the same physical network, an interface acts as a gateway between multiple subnets)

**Related commands:** SHOW INTERFACE, SET INTERFACE

**Applies to:** Routing

#### Format

```
SET CONFIGURATION [NO]INTERFACE interface
                               [/[NO]ARP ]
                               [/[NO]AUTO_START ]
                               [BROADCAST_MASK=IP_address ]
                               [C_BROADCAST_MASK=IP_address]
                               [C_NETWORK=IP_address ]
                               [/[NO]CLUSTER=host ]
                               [/COMPRESS=options ]
                               [DESTINATION=IP_address ]
                               [/[NO]DHCP ]
                               [/FLOWCONTROL ]
                               [/HOST=host ]
                               [/[NO]LOOPBACK ]
                               [NETWORK_MASK=IP_address ]
                               [/[NO]PRIMARY ]
                               [/SERIAL_DEVICE=device ]
```

#### Restrictions

This command requires:

- OPER privilege
- Read access to the hosts database
- Read access to the networks database
- Read, write, and delete access to the routes database

Every host on the same network must have the same network mask.

#### Parameters

***interface***  
Required.

Specifies an interface name for the communication controller, such as RF1, RT1, ZE0, XE0, SL0, SL1, SL2, PP0, PP1, PP2. See the chapter on configuring network interfaces in the *Compaq TCP/IP Services for OpenVMS Management* manual for more information.



### Qualifiers

**/ARP**

**/NOARP**

Optional. Default: /ARP.

Enables IP address-to-hardware address (Ethernet or FDDI) mapping.

/ARP is valid when you create an interface but not when you modify an existing interface.

**/AUTO\_START**

**/NOAUTO\_START**

Optional. Default: /AUTO\_START.

Valid for a SLIP or PPP interface. Automatically creates the interface when TCP/IP Services starts.

**/BROADCAST\_MASK=IP\_address**

Optional.

Sets the Internet interface to receive all broadcast messages.

TCP/IP Services calculates the default by the following methods:

- Using the network number
- Setting all bits in the host number field to 1

**/C\_BROADCAST\_MASK=IP\_address**

Optional.

Sets the cluster broadcast mask to receive all broadcast messages.

The software calculates the default by the following methods:

- Using the network number
- Setting all bits in the host number field to 1

**/C\_NETWORK=IP\_address**

Optional.

Sets the network mask of the cluster network. This mask is specific to the cluster host network.

The software calculates the default by using the following methods:

- Setting the bits representing the network fields to 1
- Setting the bits representing the host field to 0

**/CLUSTER=host**

**/NOCLUSTER**

Optional. Default: None.

Specifies the cluster host name (alias host identifier).

Before using this qualifier, first define the same name in the hosts database.

/CLUSTER=host associates the alias host identifier with each interface in a cluster.

## SET CONFIGURATION INTERFACE

`/NOCLUSTER` disables Internet cluster processing on the specified interface.

---

### Caution

---

When you specify `/NOCLUSTER`, active communication is aborted for applications bound to the cluster alias name.

---

### **`/COMPRESS= {ON | OFF | AUTOMATIC}`**

Optional. Defaults: For PPP interface, `/COMPRESS=ON`; for SLIP interface, `/COMPRESS=OFF`.

Valid for SLIP and PPP interfaces.

Enables or disables TCP header compression.

`/COMPRESS=AUTOMATIC` turns off compression unless the remote end begins to use it.

### **`/DESTINATION=IP_address`**

Optional.

Valid for a PPP interface.

Used on the local host to provide dialup access to remote systems. The value specified is the IP address to be given to remote clients for use while the PPP connection is active. If using `/DESTINATION`, you must provide the address of the local host by using the `/HOST` qualifier.

### **`/DHCP`**

### **`/NODHCP`**

Optional.

Designates the interface as a DHCP-controlled interface in the permanent database.

### **`/FLOWCONTROL`**

Optional. Default: No flow control.

Valid for a SLIP interface. Enables the handling of XON and XOFF characters to interoperate properly with modems that are configured to interpret these characters locally.

Specify `/FLOWCONTROL` only if the host at the other end of the line is running TCP/IP Services.

### **`/HOST=host`**

Required when first setting the interface; optional if the interface is already defined. Always required for a SLIP interface. Optional for a PPP interface unless you are setting up the local host as a dialup provider by using the `/DESTINATION` qualifier.

Local host name or IP address using the interface. If not specified for a PPP interface, PPP obtains the correct address from the remote host.

If your host is multihomed, specify an address.

## SET CONFIGURATION INTERFACE

**/LOOPBACK**

**/NOLOOPBACK**

Optional. Default: /NOLOOPBACK.

Sets loopback mode.

**/NETWORK\_MASK=IP\_address**

Required if you use subnets.

The part of the host field of the IP address identified as the subnet.

The software calculates the default by the following methods:

- Setting the bits representing the network fields to 1
- Setting the bits representing the host field to 0

An IP address consists of a network number and a host number. You can also divide the host field into a site-specific subnetwork and host field.

**/PRIMARY**

**/NOPRIMARY**

Optional.

For DHCP-controlled interfaces, designates the interface from which system-wide configuration options (such as the IP address of the BIND server) are used.

**/SERIAL\_DEVICE=device**

Required for SLIP and PPP interfaces; otherwise, not used.

Identifies the OpenVMS terminal device used as a serial device. Specify an arbitrary terminal device name. (Unlike Ethernet, FDDI, and Token Ring interface names, a serial interface name is not related to the OpenVMS device name.)

### Examples

```
1. TCPIP> SET CONFIGURATION INTERFACE SL5 /HOST=LARK -
   _TCPIP> /NETWORK_MASK=255.255.255.0 /SERIAL_DEVICE=TTA3: -
   _TCPIP> /COMPRESS=ON /FLOWCONTROL
```

Configures SLIP interface SL5, using the local IP address assigned to host LARK, with a subnet mask of 255.255.255.0.

The interface uses the terminal device TTA3:.

The /COMPRESS qualifier enables TCP header compression (CSLIP).

The /FLOWCONTROL qualifier enables special handling of XON and XOFF characters for proper interoperation with modems that are configured to interpret these characters locally.

```
2. TCPIP> SET CONFIGURATION INTERFACE FF0 /HOST=KESTREL -
   _TCPIP> /NETWORK_MASK=255.255.0.0 -
   _TCPIP> /BROADCAST_MASK=128.30.0.0 /ARP
```

For new interface FF0 on host KESTREL, sets the network mask to 255.255.0.0, sets the broadcast mask to 128.30.0.0, enables ARP, and activates the interface.

## SET CONFIGURATION INTERFACE

3. TCPIP> SET CONFIGURATION INTERFACE PPO /SERIAL\_DEVICE=TTA0: -  
\_TCPIP> /HOST=10.10.1.2 /DESTINATION=10.10.1.3

Configures the interface as a PPP serial device. This command specifies that the local host is a dialup provider. The address specified with the /DESTINATION qualifier (10.10.1.3) is the address assigned to the client system requesting an address.

See the *Compaq TCP/IP Services for OpenVMS Management* manual for more information about setting up interfaces for SLIP and PPP communication.

---

## SET CONFIGURATION MAP

Adds information to the configuration database that maps (logically links) one of the following to the NFS server:

- OpenVMS disk — Requires one execution of SET CONFIGURATION MAP to map the disk to a UNIX path name (logical file system).
- Container file system — Requires two executions of SET CONFIGURATION MAP. The first maps the disk, and the second maps the file system.

Mapping creates a logical file system, also called an NFS file system.

When the NFS server starts up, it issues a GENERATE MAP command, which creates the mappings for disks and container file systems; these mappings are viewable with the SHOW MAP command.

**Related commands:** ADD EXPORT, SHOW EXPORT, REMOVE EXPORT, MAP, UNMAP, SET CONFIGURATION NOMAP, SHOW MAP, SHOW CONFIGURATION MAP

### Format

```
SET CONFIGURATION MAP "file system name" logical_file_system
```

### Restrictions

Requires SYSPRV and BYPASS privileges.

### Parameters

**"*file system name*"**

Required.

Specifies the name for the file system or disk. When mapping a disk, the */path* can be only one level from the root. This parameter specifies the name by which users access the file system.

***logical\_file\_system***

Required.

Specifies the file system to make known to the NFS server.

To map an OpenVMS file system, specify its disk as follows:

```
$ SET CONFIGURATION MAP /disk disk:
```

To map a container file system, specify the disk and the directory name as follows:

```
TCPIP> SET CONFIGURATION MAP /container_name -
_TCPIP> disk:[vms.directory.name]
```

### Examples

1. TCPIP> SET CONFIGURATION MAP */usr* CANARY\$DUA2:

Maps local disk CANARY\$DUA2: to */usr*. This disk can be exported to users on remote NFS clients as */usr*.

## SET CONFIGURATION MAP

2. TCPIP> SET CONFIGURATION MAP "/remote" VERDIN\$DUA3: -  
\_TCPIP> SET CONFIGURATION MAP "/flyers" VERDIN\$DUA3:[UNIX\_BIRD\_FILES]

**Maps [UNIX\_BIRD\_FILES], a container file system on disk VERDIN\$DUA3:, to /flyers. This file system can be exported to NFS server users as /flyers. (The first MAP command maps the underlying OpenVMS file system.)**

---

## SET CONFIGURATION NAME\_SERVICE

When TCP/IP Services starts up, configures the BIND resolver and designates a BIND server. All settings are systemwide.

**Related commands:** SET NAME\_SERVICE,  
SHOW CONFIGURATION NAME\_SERVICE

### Format

```
SET CONFIG [NO]NAME_SERVICE [ /[NO]SERVER=host]
                               [ /[NO]DOMAIN=domain ]
                               [ /[NO]PATH=domain ]
                               [ /RETRY=number of retries ]
                               [ /TIMEOUT=seconds ]
                               [ /TRANSPORT=protocol ]
```

### Qualifiers

**/CLUSTER=dev:[directory]**

Optional.

Specifies the common BIND directory. By default, the clusterwide common database *common-disk:[TCPIP\$BIND\_common]* is used. This qualifier reloads the BIND database on every master BIND server running the OpenVMS cluster.

**/DOMAIN=domain**

**/NODOMAIN**

Optional. Default: The local domain.

Defines the default domain.

/NODOMAIN deletes the definition of the domain.

**/PATH=domain**

**/NOPATH=domain**

Optional. SYSNAM privilege is required for this command.

Defines the BIND resolver domain search list. The /NOPATH qualifier removes domains from the list.

To specify multiple domains, list them by search preference. The resolver starts with the first domain on the list, and continues to search each domain until the name is found (or until all domains have been exhausted and the lookup fails).

If you define a domain list and then issue another SET CONFIGURATION NAME\_SERVICE /PATH command, TCP/IP Services appends the new domains to the end of the list.

If a search list is not defined, the default behavior of the BIND resolver is to do a lookup on the name as you typed it. If that lookup fails, then the default domain is appended and the lookup is attempted again.

**/RETRY=number of retries**

Optional. Default: Four retries.

Number of times that the BIND resolver attempts to contact a BIND server if previous tries failed.

## SET CONFIGURATION NAME\_SERVICE

**/SERVER=host**  
**/NOSERVER=host**  
Optional.

Host name or address of the BIND server or servers that the BIND resolver will query.

To specify multiple hosts, list them by request preference. The resolver sends the first lookup request to the first host on the list.

**/NOSERVER** removes hosts from the list.

If you define a server list and then issue another SET CONFIGURATION NAME\_SERVICE /SERVER command, TCP/IP Services appends the new servers to the end of the list.

**/TIMEOUT=seconds**  
Optional. Default: 4 seconds.

Timeout interval for the BIND resolver's requests to a BIND server. Represents the length of time to wait for a reply after each retry attempt.

The total timeout period will be:

*timeout\_value \* retry\_value \* number\_servers*

**/TRANSPORT=protocol**  
Optional. Default: UDP.

Protocol used for communicating with a BIND server. Specify one:

- UDP
- TCP

### Examples

1. TCPIP> SET CONFIGURATION NAME\_SERVICE /SERVER=(PARROT,SORA,JACANA)

When TCP/IP Services starts, defines hosts PARROT, SORA, and JACANA as BIND servers.

2. TCPIP> SET CONFIGURATION NAME\_SERVICE /SERVER=OSPREY -  
\_TCPIP> /PATH=(abc.dec.com,xyz.dec.com)

When TCP/IP Services starts, defines host OSPREY as the BIND server. The BIND resolver searches the abc.dec.com domain first, and then searches the xyz.dec.com domain.



---

## SET CONFIGURATION NOMAP

Removes map records from the configuration database that were previously added with SET CONFIGURATION MAP. When the NFS server starts up, it issues a GENERATE MAP command that creates the mappings for disks and container file systems.

**Related commands:** SET CONFIGURATION MAP, SHOW CONFIGURATION MAP, ADD EXPORT, SHOW EXPORT, REMOVE EXPORT, MAP, UNMAP, SHOW MAP

### Format

```
SET CONFIGURATION NOMAP "/path/name" [ /[NO]CONFIRM ]
```

### Restrictions

Requires SYSPRV and BYPASS privilege.

### Parameters

*"/path/name"*

Required.

UNIX name of the file system to unmap.

You can use wildcards.

### Qualifiers

**/CONFIRM**

**/NOCONFIRM**

Optional. Default: /CONFIRM if you use a wildcard.

Requests confirmation before unmapping each file system.

### Examples

```
1. TCP/IP> SET CONFIGURATION NOMAP "/disk_host"
```

Unmaps the NFS file system */remote*, making it unavailable to client users when TCP/IP Services starts.

## SET CONFIGURATION PROTOCOL

---

### SET CONFIGURATION PROTOCOL

Enters information into the configuration database that sets the parameters for ICMP, IP, TCP, and UDP when TCP/IP Services starts up.

**Related commands:** SET PROTOCOL, SHOW CONFIGURATION PROTOCOL

#### Format

```
SET CONFIGURATION PROTOCOL ICMP [ /[NO]REDIRECT ]
SET CONFIGURATION PROTOCOL IP [ /[NO]FORWARD ]
                               [ /REASSEMBLY_TIMER=seconds ]
SET CONFIGURATION PROTOCOL TCP [ /[NO]MTU_SEGMENT_SIZE ]
                               [ /[NO]DELAY_ACK ]
                               [ /DROP_COUNT=seconds ]
                               [ /PROBE_TIMER=seconds ]
                               [ /QUOTA=[ SEND=bytes,RECEIVE=bytes ] ]
                               [ /[NO]WINDOW_SCALE ]
SET CONFIGURATION PROTOCOL UDP [ /[NO]BROADCAST ]
                               [ /[NO]FORWARD ]
                               [ /QUOTA=options ]
```

#### Restrictions

Requires OPER privilege.

#### Parameters

{ICMP | IP | TCP | UDP}

Required.

Specifies the protocol software to configure.

#### ICMP Qualifiers

**/REDIRECT**

**/NOREDIRECT**

Optional. Default: /NOREDIRECT.

Sends ICMP\_REDIRECT messages.

#### IP Qualifiers

**/FORWARD**

**/NOFORWARD**

Optional. Default: /NOFORWARD.

Forwards IP messages to other hosts.

**/REASSEMBLY\_TIMER=*n***

Optional. Default: 7 seconds. Valid range: 1 to 126.

Sets the maximum time for trying to reassemble a received datagram.

## TCP Qualifiers

**/MTU\_SEGMENT\_SIZE**

**/NOMTU\_SEGMENT\_SIZE**

Optional. Default: /NOMTU\_SEGMENT\_SIZE.

If a connection is more than one hop away, sets the segment size. Specify one of the following:

**/MTU\_SEGMENT\_SIZE**                Sets the segment size as close as possible to the maximum transfer unit (MTU) size.

**/NOMTU\_SEGMENT\_SIZE**            Sets the segment size as close as possible to the standard 512 bytes.

**/DELAY\_ACK**

**/NODELAY\_ACK**

Optional. Default: /DELAY\_ACK.

Enables or disables a delay before sending acknowledgments:

**/DELAY\_ACK**                        ACKs are generated with a delay.

**/NODELAY\_ACK**                    ACKs are generated without any delay.

**/DROP\_COUNT=*n***

Optional. Default: 10 minutes.

Specifies the maximum number of seconds to probe for idle TCP connections before a TCP connection close times out.

**/PROBE\_TIMER=*n***

Optional. Default: 75 seconds.

Specifies the number of seconds between probes for idle TCP connections. Also indicates the maximum number of seconds before a TCP connection request times out.

**/QUOTA=[SEND=*bytes*,RECEIVE=*bytes*]**

Optional.

Specifies the queue size (in bytes) for messages.

The options for setting TCP message queue size are:

- **RECEIVE:*n*** — Receive queue size. Default: 4096 bytes.
- **SEND:*n*** — Send queue size. Default: 4096 bytes.

**/WINDOW\_SCALE**

**/NOWINDOW\_SCALE**

Optional.

Turns TCP window scaling on and off. Default is on.

Scaling allows windows larger than 64 KB to be represented in the normal 16-bit TCP window field. Large windows allow improved throughput. Turning this option off may help troubleshoot communication problems with another TCP/IP implementation.

## SET CONFIGURATION PROTOCOL

### UDP Qualifiers

**/BROADCAST**

**/NOBROADCAST**

Optional. Default: /NOBROADCAST.

Enables privilege checking for broadcast messages.

- /BROADCAST — Nonprivileged users can send broadcast messages.
- /NOBROADCAST — To send broadcast messages, users need a privileged UIC or SYSPRV, BYPASS, or OPER privilege.

Sun RPC applications use broadcast messages and need privilege checking disabled.

**/FORWARD**

**/NOFORWARD**

Optional. Default: /NOFORWARD.

Forwards IP messages.

**/QUOTA=*options***

Optional.

Specifies the queue size (in bytes) for messages.

The options for setting UDP message queue size are:

- RECEIVE:*n* — Receive queue size. Default: 9000 bytes.
- SEND:*n* — Send queue size. Default: 9000 bytes.

### Examples

1. TCPIP> SET CONFIGURATION PROTOCOL IP /FORWARD

Sets IP to forward messages to other hosts, including other Internet cluster nodes.

2. TCPIP> SET CONFIGURATION PROTOCOL TCP /PROBE\_TIMER=50

Sets the TCP protocol probe timer parameter to 50 seconds.

---

## SET CONFIGURATION SMTP

Modifies the SMTP configuration in the configuration database.

SET CONFIGURATION NOSMTP with no qualifiers deletes all SMTP records.

**Related commands:** SHOW CONFIGURATION SMTP

### Format

```
SET CONFIGURATION [NO]SMTP [ /ADDRESS_RETRIES=n ]
                        [ /GATEWAY=option=host ]
                        [ /HOP_COUNT_MAXIMUM=n ]
                        [ /INTERVAL=options ]
                        [ /[NO]LOG=file ]
                        [ /OPTIONS=options ]
                        [ /QUEUES=n ]
                        [ /RECEIVE_TIMEOUT=minutes ]
                        [ /SEND_TIMEOUT=minutes ]
                        [ /SUBSTITUTE_DOMAIN=options ]
                        [ /[NO]ZONE[=domain] ]
```

### Restrictions

For clusters, issue this command only on the nodes where the SMTP queues reside — that is, on nodes that are not using clusterwide queues and are not managing clusterwide queues for other nodes.

Requires SYSPRV or BYPASS privilege.

### Qualifiers

#### **/ADDRESS\_RETRIES=*n***

Optional. Default: 16.

Maximum number of different addresses to which SMTP will send as it tries to deliver mail. Beyond this number of attempts, the message is undeliverable.

A message is also undeliverable if SMTP fails to deliver after it attempts all the possible addresses from an MX lookup.

#### **/GATEWAY=*option=host***

Optional. Default: None.

An alternate route through which SMTP sends mail if delivery fails.

- [NO]ALTERNATE=*host*
  - Alternate host or domain to which delivery is attempted.
  - Used by ZONE, if a zone is defined, as the last chance for delivery (see the /ZONE qualifier).
  - NOALTERNATE deletes an existing alternate destination.
- [NO]GENERAL\_PURPOSE=*host*
  - Gateway to handle non-SMTP mail, for example, UUCP addresses.

## SET CONFIGURATION SMTP

- NOGENERAL\_PURPOSE deletes the specified destination for protocols other than SMTP.

### **/HOP\_COUNT\_MAXIMUM=*n***

Optional. Default: 16.

Maximum number of relays (hops) between routers until SMTP considers the mail undeliverable.

### **/INTERVAL={ INITIAL="*OpenVMS\_delta\_time*" | RETRY="*OpenVMS\_delta\_time*" | MAXIMUM="*OpenVMS\_delta\_time*" }**

Optional. Defaults: INITIAL=30 minutes, RETRY=60 minutes, MAXIMUM=3 days.

Time intervals related to repeated attempts before delivery fails. Specify the value within quotation marks as follows: "*dddd hh:mm:ss:cc*." For example:

*dddd* = days (0–9999)

*h* = hours (0–24)

*m* = minutes

*s* = seconds

*cc* = milliseconds

You can modify the following options:

- INITIAL="*OpenVMS\_delta\_time*" is the amount of time that SMTP waits before making a second attempt to deliver.
- RETRY="*OpenVMS\_delta\_time*" is the time SMTP waits between retries, starting with the second attempt. (Recommended time: twice the initial interval.)
- MAXIMUM="*OpenVMS\_delta\_time*" is the maximum elapsed time that SMTP retries delivery.

### **/LOG=[*file*]**

### **/NOLOG=[*file*]**

Optional. Default: SYS\$SPECIFIC:[TCPIP\_SMTP]TCPIP\$SMTP\_LOGFILE.LOG.

File to which SMTP queue activity is logged.

### **/OPTIONS=*options***

Optional. Defaults: NOEIGHT\_BIT, HEADERS, NORELAY.

The following SMTP options are available:

- [NO]EIGHT\_BIT  
All characters must have the eighth bit clear. Allows the transmission of 8-bit characters.
- Header control. Specify one of the following:

HEADERS	Headers are printed at bottom of messages.
NOHEADERS	Headers are omitted.
TOP_HEADERS	Headers are printed at top of messages.
NOTOP_HEADERS	Resets TOP_HEADERS to the default.
- [NO]RELAY

## SET CONFIGURATION SMTP

Relays mail to other hosts by functioning as an end node.

### **/QUEUES=*n***

Optional. Default: 1.

Number of execution queues for the specified nodes.

Use this qualifier only on nodes that own the SMTP queues — that is, nodes not using clusterwide SMTP queues or managing SMTP clusterwide queues for other nodes.

### **/RECEIVE\_TIMEOUT=*minutes***

Optional. Default: 5 minutes.

Maximum time between socket receipts of a message for a particular dialog.

If a message is not received within this interval, the connection is broken and the mail control file is deleted.

### **/SEND\_TIMEOUT=*minutes***

Optional. Defaults:

DATA — 3 minutes  
INITIAL — 5 minutes  
MAIL — 5 minutes  
RECEIPT — 5 minutes  
TERMINATION — 10 minutes

Maximum time between remote host acknowledgments of a particular SMTP command.

If an acknowledgment is not received within the specified time, it is assumed that there are communication problems with the remote host. If the next delivery attempt takes place before the mail's delivery date, the mail is rescheduled for later delivery.

### **/SUBSTITUTE\_DOMAIN=(*[NO]NAME=fully\_qualified\_domain* | *[NO]HIDDEN*)**

Optional.

- **/SUBSTITUTE\_DOMAIN=NOHIDDEN**

In the From: and Return-Path fields, displays the sender's name and fully qualified domain.

- **/SUBSTITUTE\_DOMAIN=HIDDEN**

In the From and Return-Path fields, substitutes the value given in name for the host name. The following example shows how this qualifier can be used.

For this example, the sender's host is configured with **/SUBSTITUTE\_DOMAIN=HIDDEN,NAME=eagle**. User magpie on host condor.hawk.eagle.org sends mail to daw on another host. When it arrives, it appears to be from magpie@eagle, rather than magpie@condor.hawk.eagle.org.

This is what daw sees:

```
#707          18-NOV-2000 14:02:02.71          MAIL
From:  SMTP%"magpie@eagle"
To:    SMTP%"daw@crow.ravin.rook.org"
CC:
Subj:  Big sale today!
```

## SET CONFIGURATION SMTP

**/ZONE[=*domain*]**

**/NOZONE[=*domain*]**

Optional. Default: /NOZONE (no gateway searching).

Domain for your environment (probably a superset of your local domain).

Mail sent to another network must be sent to this gateway.

With no value, /ZONE defaults to one level higher than your local domain.

For example, if your local domain is a.b.com, the default value of /ZONE is b.com because TCP/IP Services has been started; this assumes that the domain is known.

Mail for delivery outside of your zone is sent to its destination by the alternate gateway (see the /GATEWAY qualifier).

### Examples

1. TCPIP> SET CONFIGURATION SMTP /INTERVAL=(INIT="0 00:10:00.00")

The system waits 10 minutes before making its first attempt to deliver the message.

2. TCPIP> SET CONFIGURATION SMTP /INTERVAL=(RETRY="0 00:20:00.00")

Specifies the wait time between retries.

3. TCPIP> SET CONFIGURATION SMTP /INTERVAL=(MAX="3 00:20:00.00")

Specifies the maximum amount of time to retry before an error message is issued.

4. TCPIP> SET CONFIGURATION SMTP /GATEWAY=(ALTERNATE:route\_gateway)

Specifies the alternate host or domain to which delivery is attempted if mail cannot be delivered to the primary destination.

5. TCPIP> SET CONFIGURATION SMTP /GATEWAY=(GENERAL:uucp\_gateway)

Specifies a general-purpose gateway to handle non-SMTP mail.

6. TCPIP> SET CONFIGURATION SMTP /ZONE=rsch.opt.com

Specifies that rsch is a domain that can be used to divert messages to nodes outside the local domain.



---

## SET CONFIGURATION SNMP

Configures SNMP on an individual host.

SET CONFIGURATION NOSNMP does not require any qualifiers.

After making changes to the SNMP configuration, shut down and restart the master agent and any subagents. Issue the following commands:

```
$ @SYS$STARTUP:TCPIP$SNMP_SHUTDOWN
```

```
$ @SYS$STARTUP:TCPIP$SNMP_STARTUP
```

**Related command:** SHOW CONFIGURATION SNMP

### Format

```
SET CONFIGURATION [NO]SNMP [ /NOADDRESS=host ]
                        [ /NOCOMMUNITY="name" ]
                        [ /NOCONFIRM ]
                        [ /CONTACT=name ]
                        [ /FLAGS=options ]
                        [ /LOCATION=options ]
                        [ /TYPE=options ]
```

### Restrictions

Requires SYSPRV or BYPASS privilege.

If you add a new community and do not specify the /TYPE qualifier, the value of /TYPE defaults to read only.

If you add a new community and do not specify the /ADDRESS qualifier, the default address is 0.0.0.0.

### Qualifiers

**/ADDRESS=(*IP\_address*)**

**/NOADDRESS=(*IP\_address*)**

Optional. Default: 0.0.0.0

Specifies hosts that belong to a particular community. You can specify multiple addresses.

This qualifier is meaningful only if you include the /COMMUNITY qualifier. A remote host cannot access information from this host unless its address appears in one or more communities of type READ or WRITE. For communities of type TRAP, the addresses specify the hosts that receive trap messages. For more information, see the /TYPE qualifier.

If you add a new community and do not specify this qualifier, the new entry's address is 0.0.0.0.

If you use the /ADDRESS qualifier with a community that already exists, these addresses are added to the existing address list.

/NOADDRESS deletes addresses from an existing list. If the deleted address is the only address listed for the community name, this qualifier also deletes the community.

## SET CONFIGURATION SNMP

**/COMMUNITY=*name***

**/NOCOMMUNITY=*name***

Optional. Default: To enable the standard "public" community, you can run the TCPIP\$CONFIG procedure.

Used with the /ADDRESS qualifier. Name of the community that the SNMP agent recognizes. Optionally, specify a type of access and a list of host addresses. Enclose the name in quotation marks to preserve lowercase characters. See the /TYPE and /ADDRESS qualifiers for more information.

[NO]COMMUNITY=*name* removes a community name.

**/CONFIRM**

**/NOCONFIRM**

Optional. Default: /CONFIRM with wildcards; otherwise, /NOCONFIRM

When you delete communities (with the /NOCOMMUNITY qualifier), first asks for your confirmation.

**/CONTACT=*name***

Optional. Default: None.

Name of the system administrator (or other contact person) of the host on which the SNMP agent runs. The *name* field has a maximum length of 235.

**/FLAGS=*options***

Optional.

The options include:

- SETS  
Lets the master agent process SET commands from SNMP clients.
- AUTHEN\_TRAPS  
Lets the master agent send trap messages in response to unauthorized community strings from SNMP clients.

**/LOCATION=*options***

Optional. Default: None.

Location of the system on which the SNMP agent runs. Maximum total length is 215 characters.

The options include:

- [NO]FIRST=*text*  
Specifies the first part of the location. Maximum length of *text* is 200 characters.
- [NO]SECOND=*text*  
Specifies the last part of the location. Maximum length of *text* is 200 characters.

If you specify two options, they are appended when sent to a client in response to an SNMP request for syslocation. For example, if FIRST is **abc** and SECOND is **def**, the value of the location is **abcdef** with no spaces. The total number of characters must not exceed 215.

**/TYPE= {[NO]READ | [NO]TRAP | [NO]WRITE}**

Optional. Default: READ.

Sets the type of access (to your local MIB data) to allow for a specified community.

- Type READ allows the master agent to accept GET, GETNEXT, and GETBULK commands from clients (management stations).
- Type TRAP allows the local master agent to issue traps to members of a specified community. Members of a trap community receive SNMP Trap-PDUs for significant events, including coldStart traps when the agent is initialized, and authenticationFailure traps when the agent receives an SNMP request that specifies an unauthorized community string.
- Type WRITE allows the master agent to accept SET commands from clients (management stations).

READ access is present by default when specifying TRAP or WRITE. Also, you can remove the read access without affecting the way the agent responds to a read request. For example:

```
$ SET CONFIGURATION SNMP /COMMUNITY="name" /TYPE=NOREAD
```

### Examples

1. TCPIP> SET CONFIGURATION SNMP /COMMUNITY="public" -  
    \_TCPIP> /CONTACT="Sam Spade" -  
    \_TCPIP> /LOCATION=(FIRST="Falcon Building",SECOND="Los Angeles,  
    California")

Configures SNMP with the standard public community, taking the default type (READ) and address (0.0.0.0) for that community. Both contact and location are specified.

The first and second parts of the location text are concatenated when displayed by an SNMP client. For example:

```
Falcon BuildingLos Angeles, California
```

If no update to the location text is done by an SNMP client, the display produced by SHOW CONFIGURATION SNMP is as follows:

```
Location
First: Falcon Building
Second: Los Angeles, California
```

If the text is updated by an SNMP client (for example, to change "Falcon" to "Falconi"), the original formatting is not preserved and the display produced by SHOW CONFIGURATION SNMP is as follows:

```
Location
First: Falconi BuildingLos Angeles, California
```

2. TCPIP> SET CONFIGURATION SNMP /COMMUNITY="rw" /TYPE=WRITE -  
    \_TCPIP /ADDRESS=136.20.100.10 /FLAGS=SETS

Configures a community with only read/write access to the host with the address specified. Other hosts still have read access through the public community. Also sets the SETS flag to enable the SNMP agents to process write requests from SNMP clients on host 136.20.100.10.

## SET CONFIGURATION SNMP

3. TCPIP> SET CONFIGURATION SNMP /NOCOMMUNITY="rw"

**Removes the rw (read/write) community (set in example 2.)**

4. TCPIP> SET CONFIGURATION SNMP /COMMUNITY="trapit" /TYPE=TRAP -  
\_TCPIP> /ADDRESS=136.20.0.10

**Configures SNMP so that agents can send trap messages to the well-known UDP port 162 on the host identified with the address 136.20.0.10.**

5. TCPIP> SET CONFIGURATION SNMP /FLAGS=AUTHEN\_TRAPS -  
\_TCPIP> /COMMUNITY="trapit2" /TYPE=TRAP -  
\_TCPIP> /ADDRESS=(136.20.0.12,136.20.0.15)

**Configures SNMP with the AUTHEN\_TRAPS flag so that the master agent sends trap messages when it detects a client request containing an invalid community name. Also configures an additional trap community. Trap messages, including authentication traps, go to all three addresses specified in the trap communities configured in this example and in example 4.**

6. TCPIP> SET CONFIGURATION SNMP /COMMUNITY="rw2" /TYPE=WRITE -  
\_TCPIP> /ADDRESS=(136.20.0.15,136.20.0.100)

**Configures community rw2, which gives read/write access to two hosts. Note that one address can appear for more than one community, although a given address cannot be specified more than once for a single community.**

---

## SET CONFIGURATION START ROUTING

Enters information into the configuration database to start dynamic routing when TCP/IP Services starts.

**Related commands:** SHOW CONFIGURATION START ROUTING, START ROUTING

### Format

```
SET CONFIGURATION START [NO]ROUTING [ /GATED ]
                                   [ /LOG ]
                                   [ /SUPPLY[=DEFAULT] ]
```

### Qualifiers

#### **/GATED**

Optional.

Enables the gateway routing daemon (GATED).

If you enable dynamic GATED routing, you will be able to configure this host to use any combination of the following routing protocols to exchange dynamic routing information with other hosts on the network:

- RIP (Routing Information Protocol), Versions 1 and 2
- RDISC (Router Discovery Protocol)
- OSPF (Open Shortest Path First)
- EGP (Exterior Gateway Protocol)
- BGP (Border Gateway Protocol), BGP-4
- Static routes

#### **/LOG**

Optional. Default: No logging.

Applies to ROUTED. Do not use with /GATED.

Logs routing activity to  
SYSSYSDEVICE:[TCPIP\$ROUTED]TCPIP\$ROUTED.LOG.

#### **/SUPPLY[=DEFAULT]**

Optional. Applies only to ROUTED. Do not use with /GATED.

Broadcasts routing information to other hosts in 30-second intervals.

If you specify /SUPPLY=DEFAULT, the local host supplies the default network route.

### Examples

1. TCPIP> SET CONFIGURATION START ROUTING /SUPPLY

Starts ROUTED dynamic routing when TCP/IP Services is started. The local host both broadcasts and receives network routing information.

## SET GATED

---

## SET GATED

Configures the Gateway Routing Daemon (GATED). GATED obtains information from several routing protocols and selects the best routes based on that information. These protocols are configured in the file TCPIP\$GATED.CONF.

**Related commands:** START ROUTING /GATED, STOP ROUTING /GATED

### Format

```
SET GATED [ /CHECK_INTERFACES ]
          [ /FILE=file ]
          [ /SAVE_STATE ]
          [ /TOGGLE_TRACE ]
```

### Qualifiers

#### **/CHECK\_INTERFACES**

Optional.

Instructs GATED to scan the kernel interface list for changes.

#### **/FILE=*file***

Optional.

Specifies the name of the GATED configuration file. Use with the /SAVE\_STATE qualifier.

#### **/SAVE\_STATE**

Optional.

Causes GATED to save the current state of all tasks, timers, protocols, and tables to the file SYSSYSDEVICE:[TCPIP\$GATED]TCPIP\$GATED.DMP (default).

Use the /FILE qualifier to specify a file name other than the default.

#### **/TOGGLE\_TRACE**

Optional.

Use to close the trace file. A subsequent set GATED /TOGGLE\_TRACE command reopens the trace file. This allows the file to be copied regularly. Valid only when a trace file is specified in the GATED configuration file.

### Examples

1. TCPIP> SET GATED /SAVE\_STATE

This example causes GATED to save its current state to the file SYSSYSDEVICE:[TCPIP\$GATED]TCPIP\$GATED.DMP.

2. TCPIP> SET GATED /SAVE\_STATE /FILE=STATE.DMP

This example causes GATED to save its current state to the file named STATE.DMP.

---

## SET HOST

Defines or deletes an entry in the hosts database.

Equivalent to maintaining the `/etc/hosts` file on UNIX hosts.

**Related command:** SHOW HOST, CONVERT/VMS HOST

### Format

```
SET [NO]HOST host /ADDRESS=IP_address
[ /[NO]ALIAS=alias ]
[ /[NO]CONFIRM ]
```

### Restrictions

Requires read, write, and delete access to the hosts database.

### Parameters

***host***

Required.

Name of a host that is a source or destination of internet communications.

---

**Note**

---

To define a name in lowercase or mixed case, enclose it in quotation marks.

If you define a mixed-case name, also define an alias in either all uppercase or all lowercase characters.

You cannot delete a host by specifying its alias.

---

### Qualifiers

***/ADDRESS=IP\_address***

Required for SET HOST.

Host's IP address.

***/ALIAS=alias***

***/NOALIAS=alias***

Optional.

Add or remove an alternate name for a host.

Do not use with SET NOHOST.

***/CONFIRM***

***NOCONFIRM***

Optional. Default: */CONFIRM* if you use a wildcard.

Used with the SET NOHOST command, prompts you to confirm the delete request. For example:

## SET HOST

```
TCPIP> SET NOHOST MOA /ADDRESS=11.33.33.8 /CONFIRM
      LOCAL database
Host address   Host name
11.33.33.8 MOA
Remove? [N]:
```

### Examples

1. TCPIP> SET HOST MOA /ADDRESS=11.33.33.8 -  
\_TCPIP> /ALIAS=( "moa", "bigbrd", "nofly" )  
**Sets the IP address of host MOA to 11.33.33.8 and establishes moa, bigbrd, and nofly as aliases for host MOA.**
2. TCPIP> SET HOST MOA /ALIAS="MOA\_2"  
**Establishes MOA\_2 as an alias for host MOA.**
3. TCPIP> SET HOST MOA /ADDRESS = 128.33.33.9  
**Establishes a second IP address for host MOA.**
4. TCPIP> SET HOST MOA /ADDRESS = 128.33.33.9 /ALIAS="MOA\_3"  
**Establishes MOA\_3 as an alias for host MOA's second IP address 128.33.33.9.**
5. TCPIP> SET HOST MOA /NOALIAS="MOA\_2"  
**Deletes MOA\_2 as an alias for host MOA.**
6. TCPIP> SET NOHOST MOA /NOCONFIRM  
**Deletes MOA and all of its associated aliases.**



---

## SET INTERFACE

Defines one of the following:

- An Internet interface
- A serial line IP (SLIP) or point-to-point (PPP) connection
- A pseudointerface (a data structure that extends subnet routing)

Before you issue SET INTERFACE, do the following to identify the name of an interface:

- Issue the LIST COMMUNICATION\_CONTROLLER command to find your system's controller.
- Use the first character of the associated interface name.

See the *Compaq TCP/IP Services for OpenVMS Management* manual for more information about specifying an interface name.

SET NOINTERFACE deletes a record. No qualifiers are required.

**Related commands:** SHOW INTERFACE, SET CONFIGURATION INTERFACE

### Format

```
SET [NO]INTERFACE interface
    [ /NO]ARP ]
    [ /NO]AUTO_START ]
    [ /BROADCAST_MASK=IP_address ]
    [ /C_BROADCAST_MASK=IP_address ]
    [ /C_NETWORK=IP_address ]
    [ /NO]CLUSTER=host ]
    [ /COMPRESS=options ]
    [ /DESTINATION=IP_address ]
    [ /DHCP ]
    [ /FLOWCONTROL ]
    [ /HOST=host ]
    [ /NO]LOOPBACK ]
    [ /NETWORK_MASK=IP_address ]
    [ /PRIMARY ]
    [ /SERIAL_DEVICE=device ]
```

### Restrictions

Before you issue the SET INTERFACE command, disable the interface by using the SET NOINTERFACE command.

This command requires:

- OPER privilege
- Read access to the hosts database
- Read access to the networks database
- Read, write, and delete access to the routes database

Every host on the same network must have the same network mask.

## SET INTERFACE

### Parameters

***interface***

Required.

Specifies an interface name for the communication controller, such as RF1, RT1, ZE0, XE0, SL0, SL1, SL2, PP0, PP1, PP2.

### Qualifiers

**/ARP**

**/NOARP**

Optional. Default: /ARP.

Enables IP address-to-hardware address (Ethernet or FDDI) mapping.

/ARP is valid when you create an interface but not when you modify an existing interface.

**/AUTO\_START**

**/NOAUTO\_START**

Optional. Default: /AUTO\_START.

Valid for a SLIP or PPP interface. Automatically creates the interface when TCP/IP Services starts.

**/BROADCAST\_MASK=*IP\_address***

Optional.

Sets the Internet interface to receive all broadcast messages.

TCP/IP Services calculates the default by:

- Using the network number from the network mask
- Setting all bits in the host number field to 1

**/C\_BROADCAST\_MASK=*IP\_address***

Optional.

Sets the cluster broadcast mask to receive all broadcast messages.

The software calculates the default by:

- Using the network number from the network mask
- Setting all bits in the host number field to 1

**/C\_NETWORK=*IP\_address***

Optional.

Sets the network mask of the cluster network. This mask is specific to the cluster host network.

The software calculates the default by:

- Setting the bits representing the network fields to 1
- Setting the bits representing the host field to 0

**/CLUSTER=*host***

**/NOCLUSTER**

Optional. Default: None.

Specifies the cluster host name (alias host identifier).

Before using this qualifier, first define the same name in the hosts database.

*/CLUSTER=host* associates the alias host identifier with each interface in a cluster.

*/NOCLUSTER* disables internet cluster processing on the specified interface.

---

### Caution

---

When you specify */NOCLUSTER*, active communication is aborted for applications bound to the cluster alias name.

---

### ***/COMPRESS= {ON | OFF | AUTOMATIC}***

Optional. Default: For PPP interface: */COMPRESS=ON*; for SLIP interface: */COMPRESS=OFF*

Valid for SLIP and PPP interfaces.

Enables or disables TCP header compression.

*/COMPRESS=AUTOMATIC* turns off compression unless the remote end begins to use it.

### ***/DESTINATION=IP\_address***

Optional.

Valid for a PPP interface.

Used on the local host to provide dialup access to remote systems. The value specified is the IP address to be given to remote clients for use while PPP connection is active. If you use */DESTINATION*, you must provide the address of the local host with the */HOST* qualifier.

### ***/DHCP***

Optional.

Designates the interface as a DHCP-controlled interface in the volatile database. This qualifier affects only the currently running interface.

Before you enter the SET INTERFACE command, be sure to enter the SET NOINTERFACE command first and specify the interface you are changing.

### ***/FLOWCONTROL***

Optional. Default: No flow control.

Valid for a SLIP interface. Enables the handling of XON and XOFF characters to properly interoperate with modems that are configured to interpret these characters locally.

Specify */FLOWCONTROL* only if the host at the other end of the line is another host running TCP/IP Services.

### ***/HOST=host***

Required when first setting the interface; optional if the interface is already defined. Always required for a SLIP interface. Optional for a PPP interface unless you are setting up the local host as a dialup provider by using the */DESTINATION* qualifier.

## SET INTERFACE

Local host name or IP address using the interface. If this information is not specified for a PPP interface, PPP obtains the correct address from the remote host.

If your host is multihomed, specify an address.

**/LOOPBACK**

**/NOLOOPBACK**

Optional. Default: /NOLOOPBACK.

Sets loopback mode.

**/NETWORK\_MASK=IP\_address**

Required if you use subnets.

The part of the host field of the IP address identified as the subnet.

The software calculates the default by:

- Setting the bits representing the network fields to 1
- Setting the bits representing the host field to 0

An IP address consists of a network number and a host number. You can also divide the host field into a site-specific subnetwork and host field.

**/PRIMARY**

Optional.

For DHCP-controlled interfaces, designates the interface from which system-wide configuration options (such as the IP address of the BIND server) are used.

**/SERIAL\_DEVICE=device**

Required for SLIP and PPP interfaces; otherwise not used.

Identifies the OpenVMS terminal device used as a serial device. Specify an arbitrary terminal device name. (Unlike Ethernet, FDDI, and Token Ring interface names, a serial interface name is not related to the OpenVMS device name.)

## Examples

1. `TCPIP> SET INTERFACE SL5 /HOST=LARK /NETWORK_MASK=255.255.255.0 -  
_TCPIP> /SERIAL_DEVICE=TTA3: /COMPRESS=ON /FLOWCONTROL`

Configures SLIP interface SL5, using the local IP address assigned to host LARK, with a subnet mask of 255.255.255.0.

The interface uses the terminal device TTA3:.

The /COMPRESS qualifier enables TCP header compression (CSLIP).

The /FLOWCONTROL qualifier enables special handling of XON and XOFF characters, to ensure proper interoperability with modems that are configured to interpret these characters locally.

2. `TCPIP> SET INTERFACE FF0 /HOST=KESTREL /NETWORK_MASK=255.255.0.0 -  
_TCPIP> /BROADCAST_MASK=128.30.255.255 /ARP`

For new interface FF0 on host KESTREL, sets the network mask to 255.255.0.0, sets the broadcast mask to 128.30.0.0, enables ARP, and activates the interface.

## SET INTERFACE

3. TCPIP> SET INTERFACE PP0 /SERIAL\_DEVICE=TTA0: -  
\_TCPIP> /HOST=10.10.1.2 /DESTINATION=10.10.1.3

Configures the interface as a PPP serial device. This command specifies that the local host is a dialup provider. The address specified with the /DESTINATION qualifier (10.10.1.3) is the address assigned to the client system requesting an address.

See *Compaq TCP/IP Services for OpenVMS Management* manual for more information on setting up interfaces for SLIP and PPP communication.

4. TCPIP> SET NOINTERFACE DE2  
TCPIP> SET INTERFACE DE2 /LOOPBACK  
. . .  
TCPIP> SET INTERFACE DE2

Deletes interface DE2, sets loopback mode for testing this interface, and, after testing, reactivates it.

## SET MX\_RECORD

---

## SET MX\_RECORD

For routing mail, adds routing information to the local Mail Exchanger (MX) database.

Each entry contains a list of hosts that can accept mail for the specified destination. The list is in order of routing preference.

The local MX information is stored in the routes database.

The MX entry is one of the record types in the BIND database. In addition, a BIND server might provide an MX record.

SMTP is designed to determine where the sending system should try to relay mail. It is also designed to identify where the sending system actually tries to relay mail. To find a destination address, the MX routing lookup process follows this sequence:

1. Local MX database
2. Remote MX database
3. BIND database
4. Local hosts database

**Related command:** SHOW MX\_RECORD

### Formats

```
SET MX_RECORD destination /GATEWAY=host /PREFERENCE=n
```

```
SET NOMX_RECORD [ destination ]  
                [ /GATEWAY=host ]
```

### Restrictions

Requires read and write access to the routes database.

### Parameters

***destination***

Required for SET MX\_RECORD.

Optional for SET NOMX\_RECORD.

Host name or domain name to which mail will be sent.

### Qualifiers

***/GATEWAY=host***

Required with SET MX\_RECORD. Do not use with SET NOMX\_RECORD.

Gateway through which mail will be relayed. Must have an address in either the local hosts database or the BIND database.

A destination can have multiple gateways, each with an associated preference value.

***/PREFERENCE=n***

Required.

Arbitrary number for ranking multiple gateways for a destination. The smaller the number, the higher the preference in sending mail by way of that gateway.

Do not use with SET NOMX\_RECORD.

### Examples

1. TCPIP> SET MX\_RECORD JUNO /GATEWAY=MARS /PREFERENCE=100

Assigns MARS as the gateway for host JUNO with a preference of 100.

2. TCPIP> SET MX\_RECORD JUNO /GATEWAY=VENUS /PREFERENCE=200

Assigns VENUS as the gateway for host JUNO with a preference of 200.

## SET NAME\_SERVICE

---

## SET NAME\_SERVICE

Configures the BIND resolver and designates a BIND server. By default, all settings are process specific.

- To make modifications that are systemwide, use the /SYSTEM qualifier.
- The local host's domain is used as the default domain unless you also specify /DOMAIN.
- To reload the BIND server databases, use the /INITIALIZE qualifier.
- /NOSERVER does not require any options.

**Related commands:** SHOW NAME\_SERVICE,  
SET CONFIGURATION NAME\_SERVICE

### Format

```
SET NAME_SERVICE [ /CLUSTER=dev:directory ]  
                 [ /DISABLE ]  
                 [ /[NO]DOMAIN=domain ]  
                 [ /ENABLE ]  
                 [ /INITIALIZE ]  
                 [ /[NO]PATH=domain ]  
                 [ /RETRY=number of retries ]  
                 [ /[NO]SERVER=host ]  
                 [ /SYSTEM ]  
                 [ /TIMEOUT=seconds ]  
                 [ /TRANSPORT=protocol ] )
```

### Restrictions

The /SYSTEM qualifier requires SYSPRV or BYPASS and SYSNAM privileges.

### Qualifiers

#### **/CLUSTER=*dev*:*directory***

Optional.

Specifies the common BIND directory. By default, the clusterwide common directory is *common-disk*:*[TCPIP\$BIND\_COMMON]*. This qualifier reloads the BIND database on every master BIND server running in the OpenVMS Cluster.

This qualifier must be used with the /INITIALIZE qualifier.

#### **/DISABLE**

Optional.

Disables the BIND resolver. All name and address lookups are now directed to the local hosts database. Use with /SYSTEM.

#### **/DOMAIN=*domain***

#### **/NODOMAIN=*domain***

Optional.

Defines the default domain. The default domain is appended to host name references made from the local process.



## SET NAME\_SERVICE

**/NODOMAIN** deletes the process-specific definition of the domain. Do not use with **/SYSTEM**.

### **/ENABLE**

Optional. Default: Not enabled.

Enables the BIND resolver. Must be used with **/SYSTEM**.

### **/INITIALIZE**

Optional. Default: No reloading.

Reloads the BIND server databases.

### **/PATH=domain**

### **/NOPATH=domain**

Optional.

Defines the BIND resolver's domain search list.

To specify multiple domains, list them by search preference. The resolver starts with the first domain on the list, and continues to search each domain until the name is found or until all domains have been exhausted and the lookup fails.

**/NOPATH** removes domains from the list.

If you define a domain list and then issue another **SET NAME\_SERVICE /PATH** command, TCP/IP Services appends the new domains to the end of the list.

If no search list is defined, the default behavior of the BIND resolver is to do a lookup on the name as you typed it. If that lookup fails, then the default domain is appended and the lookup is attempted again.

### **/RETRY=number of retries**

Optional. Default: four retries.

Specifies the number of times that the BIND resolver attempts to contact a BIND server if previous tries fail.

### **/SERVER=host**

### **/NOSERVER=host**

Optional.

Specifies the host name or address of the BIND server or servers that the resolver will query.

To specify multiple hosts, list them by request preference. The resolver sends the first lookup request to the first host on the list.

**/NOSERVER** removes hosts from the list.

If you define a server list and then issue another **SET NAME\_SERVICE /SERVER** command, TCP/IP Services appends the new servers to the end of the list.

Do not use **/NOSERVER** with **/SYSTEM**.

### **/SYSTEM**

Optional. Default: Changes are process specific.

Makes your settings systemwide.

### **/TIMEOUT=seconds**

Optional. Default: 4 seconds.

## SET NAME\_SERVICE

Specifies the timeout interval for the BIND resolver's requests to a server.

When the BIND resolver is used by the auxiliary server, the following conditions are true:

- The number of retries is one.
- The timeout interval is 1 second.
- The timeout interval increases by the power of two for each retry, as shown in the following table:

Current settings: Retry	If Retries=4 and Timeout=4 Timeout interval is:
First	4 seconds
Second	8 seconds
Third	16 seconds
Last	32 seconds
	Total = 1 minute for one server
	If a second BIND server exists and both servers time out, total = 2 minutes

***/TRANSPORT=protocol***  
Optional. Default: UDP.

Protocol used for communicating with a BIND server. Specify one of the following:

- UDP
- TCP

### Examples

1. TCPIP> SET NAME\_SERVICE /SERVER=(PARROT,SORA,JACANA) /SYSTEM /ENABLE

Defines hosts PARROT, SORA, and JACANA as systemwide BIND servers.  
Also enables the BIND resolver.

2. TCPIP> SET NAME\_SERVICE /SERVER=OSPREY

For your process, defines host OSPREY as the BIND server. The servers that are defined systemwide will not be queried.

---

## SET NETWORK

Defines or deletes an entry in the networks database.

Equivalent to maintaining the `/etc/networks` file on UNIX hosts.

**Related commands:** SHOW NETWORK, CONVERT/VMS NETWORK

### Format

```
SET [NO]NETWORK network
                [ /ADDRESS=IP_address ]
                [ /[NO]ALIAS=alias ]
                [ /[NO]CONFIRM ]
```

### Restrictions

Requires read, write, and delete access to the networks database.

### Parameters

***network***

Required.

Name of the network.

You cannot delete a network by specifying an alias name.

### Qualifiers

***/ADDRESS=IP\_address***

Required for a new entry.

IP address of the network.

***/ALIAS=alias***

***/NOALIAS=alias***

Optional.

Alternate name for the network.

- Do not use with SET NONETWORK.
- */NOALIAS=alias* deletes an alias.
- */NOALIAS=\** deletes all aliases.

***/CONFIRM***

***NOCONFIRM***

Optional. Default: */CONFIRM* if you use a wildcard.

When used with SET NONETWORK, prompts you to confirm the delete request.

### Examples

```
1. TCP/IP> SET NETWORK MYNA /ADDRESS=128.30.30.10 /ALIAS=MYNA_1
```

Creates an entry for network MYNA at IP address 128.30.30.10, and its alias MYNA\_1, to the networks database.

## SET NETWORK

2. TCPIP> SET NETWORK MYNA /ALIAS=MYNA\_2  
**Adds a second alias for network MYNA.**
3. TCPIP> SET NETWORK MYNA /NOALIAS=MYNA\_2  
**Deletes the alias MYNA\_2 from the network MYNA entry in the networks database.**
4. TCPIP> SET NETWORK "jungle" /ALIAS=("parrot","canary","motmot")  
**For network jungle, creates the aliases parrot, canary, and motmot.**

---

## SET NFS\_SERVER

Modifies the parameters of the NFS server software.

You can dynamically modify some characteristics, but other values are static. Modifications take effect by shutting down and restarting the NFS server software.

- Dynamically modifiable qualifiers:
  - /GID\_DEFAULT
  - /INACTIVITY\_TIMER
  - /UID\_DEFAULT
- Static qualifiers:
  - /THREADS

To make your changes permanent, modify the `SYSSSTARTUP:TCPIP$NFS_SERVER_STARTUP.COM` file.

To shut down the NFS server, issue the following command:

```
$ @SYSSSTARTUP:TCPIP$NFS_SHUTDOWN.COM
```

To enable the server to restart, issue the following command:

```
$ @SYSSSTARTUP:TCPIP$NFS_SERVER_STARTUP.COM
```

The auxiliary server automatically restarts the NFS server upon an incoming client request.

**Related commands:** SHOW NFS\_SERVER, ZERO NFS\_SERVER

### Format

```
SET NFS_SERVER [ /GID_DEFAULT=n ]
               [ /INACTIVITY_TIMER=n ]
               [ /THREADS=n ]
               [ /UID_DEFAULT=n ]
```

### Restrictions

Requires the following privileges:

- SYSNAM
- WORLD
- SYSPRV or BYPASS

### Qualifiers

**/GID\_DEFAULT=*n***

Optional. Default: -2.

Default GID associated with files not created by the NFS server.

**/INACTIVITY\_TIMER=*n***

Optional. Default: 02:00.

## SET NFS\_SERVER

Maximum length of time that unaccessed NFS files remain open.

Specify *mm:ss*, where *mm* is the number of minutes and *ss* is the number of seconds.

**/THREADS=*n***

Optional. Default: 20.

Maximum number of simultaneous requests that the NFS server processes.

**/UID\_DEFAULT=*n***

Optional. Default: -2.

Default UID associated with files not created by the NFS server.

### Examples

1. TCPIP> SET NFS\_SERVER /INACTIVITY\_TIMER=03:00

Sets the length of time that unaccessed NFS files remain open.

---

## SET PROTOCOL

Sets parameters for ICMP, IP, TCP, and UDP.

**Related commands:** SET CONFIGURATION PROTOCOL, SHOW PROTOCOL

### Format

```
SET PROTOCOL ICMP [ /[NO]REDIRECT ]
SET PROTOCOL IP [ /[NO]FORWARD ]
                 [ /REASSEMBLY_TIMER=seconds ]
SET PROTOCOL TCP [ /[NO]MTU_SEGMENT_SIZE ]
                 [ /[NO]DELAY_ACK ]
                 [ /DROP_COUNT=seconds ]
                 [ /PROBE_TIMER=seconds ]
                 [ /QUOTA=[ SEND=bytes,RECEIVE=bytes ] ]
                 [ /[NO]WINDOW_SCALE ]
SET PROTOCOL UDP [ /[NO]BROADCAST ]
                 [ /[NO]FORWARD ]
                 [ /QUOTA=options ]
```

### Restrictions

Requires OPER privilege.

### Parameters

{ICMP | IP | TCP | UDP}

Required.

Specifies the protocol software to configure.

### Qualifiers for ICMP

**/REDIRECT**

**/NOREDIRECT**

Optional. Default: /NOREDIRECT.

Sends ICMP\_REDIRECT messages.

### Qualifiers for IP

**/FORWARD**

**/NOFORWARD**

Optional. Default: /NOFORWARD.

Forwards IP messages to other hosts.

**/REASSEMBLY\_TIMER=*n***

Optional. Default: 7 seconds. Valid range: 1 to 126.

Maximum time for trying to reassemble a received datagram.

## SET PROTOCOL

### Qualifiers for TCP

**/MTU\_SEGMENT\_SIZE**

**/NOMTU\_SEGMENT\_SIZE**

Optional. Default: /NOMTU\_SEGMENT\_SIZE.

If a connection is more than one hop away, sets the segment size. Specify one of the following:

**/MTU\_SEGMENT\_SIZE**                Sets the segment size as close as possible to the maximum transmission unit (MTU) size.

**/NOMTU\_SEGMENT\_SIZE**            Sets the segment size as close as possible to the standard 512 bytes.

**/DELAY\_ACK**

**/NODELAY\_ACK**

Optional. Default: /DELAY\_ACK.

Enables or disables a delay before sending the following acknowledgments:

**/DELAY\_ACK**                        ACKs are generated with a delay.

**/NODELAY\_ACK**                    ACKs are generated without any delay.

**/DROP\_COUNT=*n***

Optional. Default: 10 minutes.

Maximum number of seconds to probe for idle TCP connections before a TCP connection close times out.

**/PROBE\_TIMER=*n***

Optional. Default: 75 seconds.

Number of seconds between probes for idle TCP connections. Also indicates the maximum number of seconds before a TCP connection request times out.

**/QUOTA=[SEND=*bytes*,RECEIVE=*bytes*]**

Optional.

Queue size (in bytes) for messages.

The options for setting TCP message queue size are:

- **RECEIVE:*n*** — Receive queue size. Default: 4096 bytes.
- **SEND:*n*** — Send queue size. Default: 4096 bytes.

**/WINDOW\_SCALE**

**/NOWINDOW\_SCALE**

Optional.

Turns TCP window scaling on and off. Default is on.

Scaling allows windows larger than 64 KB to be represented in the normal 16-bit TCP window field. Large windows allow improved throughput. Turning this option off may help you to troubleshoot communication problems with another TCP/IP implementation.



**Qualifiers for UDP****/[NO]BROADCAST**

Optional. Default: /NOBROADCAST.

Enables privilege checking for broadcast messages.

- /BROADCAST — Nonprivileged users can send broadcast messages.
- /NOBROADCAST — To send broadcast messages, users need a privileged UIC or the SYSPRV, BYPASS, or OPER privilege.

ONC RPC applications use broadcast messages and need privilege checking disabled.

**/FORWARD****/[NO]FORWARD**

Optional. Default: /NOFORWARD.

Forwards IP messages.

**/QUOTA=*options***

Optional.

Specifies the queue size (in bytes) for messages.

The options for setting UDP message queue size are:

- RECEIVE:*n* — Receive queue size. Default: 9000 bytes.
- SEND:*n* — Send queue size. Default: 9000 bytes.

**Examples**

1. TCPIP> SET PROTOCOL IP /FORWARD

Sets IP to forward messages to other hosts, including other Internet cluster nodes.

2. TCPIP> SET PROTOCOL TCP /PROBE\_TIMER=50

Sets the TCP probe timer parameter to 50 seconds.

## SET ROUTE

---

## SET ROUTE

Defines a routing path in either the permanent or volatile routes database.

Routes in the permanent, on-disk routes database are static. Static routes can be supplemented by routes that the dynamic routing server receives. Defaults are as follows:

- If the network is not active, the command affects the permanent database.
- If the network is active, the command affects the volatile database. (To modify the permanent database, use the /PERMANENT qualifier.)

Note the following restrictions:

- You can add routes.
- You cannot use SET NOROUTE to remove a route that is maintained by the route daemon.
- To have full manual control over your routing table, first issue STOP ROUTING and then use SET NOROUTE.
- SET NOROUTE does not require any qualifiers.

**Related commands:** SHOW ROUTE, STOP ROUTING

---

### Note

---

Compaq strongly recommends that you do not specify alias names with the *destination* parameter or with the /GATEWAY=*host* qualifier.

---

## Format

```
SET [NO]ROUTE destination
                [ /[NO]CONFIRM ]
                [ /DEFAULT_ROUTE ]
                [ /GATEWAY=host ]
                [ /MASK=mask_length ]
                [ /NETWORK ]
                [ /PERMANENT ]
```

## Restrictions

Requires OPER privilege if:

- The TCP/IP Services product is running.
- The routes database requires read and write access.

## Parameters

### ***destination***

Required unless you specify the /DEFAULT\_ROUTE qualifier.

Host or network through which to route packets. Specify one of the following:

- A host, as it is defined in the hosts database
- A network, as it is defined in the networks database

Not valid with /DEFAULT\_ROUTE.

## Qualifiers

### **/CONFIRM**

### **NOCONFIRM**

Optional. Default: /CONFIRM if you use a wildcard.

Prompts you to confirm the change.

### **/DEFAULT\_ROUTE**

Optional. Default: 0.0.0.0.

Defines a second route to use if the first try to route a packet fails.

You must also specify a value for /GATEWAY.

Not valid with the *destination* parameter.

### **/GATEWAY=host**

Optional. Default: None.

Gateway for the route. Necessary to send packets to a host on another network.

### **/MASK=mask\_length**

Optional. Default: None.

Defines the Classless Inter-Domain Routing (CIDR) mask length. (The mask length is sometimes referred to as the prefix length.)

CIDR is a method of associating blocks of Internet addresses through the use of a mask. With CIDR, a route is a combination of the IP address and a value describing the length of the leftmost contiguous set of bits.

### **/NETWORK**

Optional. Defaults:

- Destination is classified based on its Internet network class (A, B, or C).
- If the address is clearly a network number, SET ROUTE interprets the number correctly.

Defines the route as a network route.

Use this qualifier if the network number could be misinterpreted as an IP host address, for example, if a network mask is nonstandard, or if the IP address is abbreviated.

### **/PERMANENT**

Optional. Defaults:

If the network is not active, the permanent routes database is changed. If the network is active, the volatile routes database is changed.

Changes only the permanent routes database.

## Examples

1. TCP/IP> SET ROUTE DODO /GATEWAY=RHEA

Defines a route for local host DODO to send packets.

## SET ROUTE

2. TCPIP> SET ROUTE 101.81 /GATEWAY=100.42

**Defines a gateway for routing packets for the host with IP address 101.81.**

3. TCPIP> SET ROUTE 100.45.0 /GATEWAY=REMOTE /NETWORK

**Sets a route through the network whose IP address is 100.45.0.**

4. TCPIP> SET ROUTE /DEFAULT /GATEWAY=DEFGATE /PERMANENT

**Sets a default route with host DEFGATE as the default gateway. Adds the definition to the permanent routes database.**

---

## SET SERVICE

Defines a new entry in the services database or modifies an existing entry.

**Related command:** SHOW SERVICE

### Format

```
SET [NO]SERVICE service
    { /FILE=startup_file*
      /PORT=n*
      /PROCESS_NAME=process*
      /USER_NAME=vms_user_account* }
    [ /ACCEPT=options ]
    [ /ADDRESS=IP_address ]
    [ /FLAGS=options ]
    [ /LIMIT=n ]
    [ /LOG_OPTIONS=options ]
    [ /PROTOCOL=protocol=options ]
    [ /REJECT=options ]
    [ /RPC=values ]
    [ /SEPARATOR=option ]
    [ /SOCKET_OPTIONS=options ]
```

### Restrictions

You cannot modify the following fields in an existing entry:

- *service*
- /ADDRESS
- /PORT
- /PROCESS\_NAME
- /PROTOCOL (except for the optional settings)

To make changes to these fields, use SET NOSERVICE to delete the entry and then re-create the entry.

---

#### Note

---

There is no RCP service. RCP uses the RSH server process.

---

Compaq strongly suggests that, for the services provided by TCP/IP Services, you do not use this command to reset the following:

- The required qualifiers
- The /FLAGS qualifier, except for the APPLICATION\_PROXY and CASE\_INSENSITIVE options

Using SET NOSERVICE without either a specified service or specified qualifiers deletes all entries for all services.

Requires write access to the directory with the services database.

# SET SERVICE

## Parameters

### **service**

Required for SET SERVICE; optional for SET NOSERVICE.

Service you want to enter into the services database. Specify a string of up to 10 characters.

## Qualifiers

**/ACCEPT {[NO]HOSTS=(*hosts*) | =[NO]NETWORKS=(*networks*)}**

Optional. Default: Offers the service to all hosts on all networks.

- **/ACCEPT=HOST=(*host*)**
  - Grants *host* or *hosts* access to the service.
  - Denies access to all other hosts.
- **/ACCEPT=NOHOST=*host*** removes access to the service for a host that previously gained access with **/ACCEPT=HOST**.

The following options are available:

Option	Meaning
HOSTS= <i>hosts</i>	Makes the service available to the specified hosts. Denies all other hosts access to the service. Maximum is 32. <b>Example:</b> <code>/ACCEPT=HOSTS=(<i>host1_name</i>,<i>host2_name</i>,<i>host3_address</i>)</code>
NOHOSTS= <i>hosts</i>	Removes the specified hosts from the accept list so they cannot gain access to the service. You can specify a wildcard character (*) in place of the <i>hosts</i> list to remove all hosts from the accept list. Maximum is 32. <b>Example:</b> <code>/ACCEPT=NOHOSTS=(<i>host1_name</i>,<i>host2_name</i>,<i>host3_address</i>)</code>
NETWORKS= <i>networks</i>	Makes the service available to the specified networks. Denies access to the service to all other networks. Maximum is 16. For each network, you can optionally specify the network mask. The default network mask equals network's class number. For example, for the network 11.200.0.0., the default mask is 255.0.0.0. <b>Example:</b> <code>/ACCEPT=NETWORKS=(<i>net1_name</i>,<i>net2_address</i>,<i>net3:net3mask</i>)</code>
NONETWORKS[= <i>networks</i> ]	Removes the specified networks from the accept list so they cannot gain access to the service. You can specify a wildcard character (*) in place of the <i>networks</i> list to remove all networks from the accept list. Maximum is 16. For each network, you can optionally specify the network mask. The default net mask equals network's class number. For example, for network 11.200.0.0., the default mask is 255.0.0.0. <code>/ACCEPT=NONETWORKS=(<i>net1_name</i>,<i>net2_address</i>,<i>net3:net3mask</i>)</code>

**/ADDRESS=IP\_address**

Optional. Default: 0.0.0.0 (all local interfaces receive incoming requests for the service).

If you have multiple Internet interfaces and, therefore, more than one IP address, /ADDRESS specifies the particular address on which incoming requests are received.

To define a service name more than once, use /ADDRESS with different values for each instance. A reason to duplicate a service name, for example, is that your local host has three interfaces and you want to make a service available on two of them. Each service/interface pair must be unique.

**/FILE=startup\_file**

Required.

Name of the service's startup command file.

**/FLAGS= {[NO]APPLICATION\_PROXY | [NO]MULTITHREAD | [NO]PROXY | [NO]CASE\_INSENSITIVE}**

Optional.

The flag options are:

- [NO]APPLICATION\_PROXY. Default: NOAPPLICATION\_PROXY.  
The service does its own proxy checking. This allows connections based on defined proxies.  
**Applies to:** remote shell (RSH) and line printer daemon (LPD).

---

**Note**

---

The ROOT account does not require a communication proxy in the proxy database. The setting of /FLAGS=APPLICATION\_PROXY flag is not relevant.

---

- [NO]MULTITHREAD. Default: NOMULTITHREAD.  
While connecting a socket to a remote host and passing the socket to the requested server, the auxiliary server continues to listen for incoming requests.
- [NO]PROXY. Default: NOPROXY.  
User account information is from the proxy database.
- [NO]CASE\_INSENSITIVE. Default: CASE\_INSENSITIVE.  
Case sensitivity of the remote user name in the proxy database.  
Use with /PROXY.

**/LIMIT=n**

Optional.

Maximum number of copies of the requested service allowed to run on the system. If the maximum number is reached, any additional requests for the service are rejected.

## SET SERVICE

```
/LOG_OPTIONS=  
[ [NO]ACCEPT ]  
[ [NO]ACTIVATE ]  
[ [NO]ADDRESS ]  
[ [NO]ALL ]  
[ [NO]CONNECT ]  
[ [NO]DEACTIVATE ]  
[ [NO]ERROR ]  
[ [NO]EXIT_CLEANUP ]  
[ [NO]LOGIN ]  
[ [NO]LOGOUT ]  
[ [NO]MODIFY ]  
[ [NO]REJECT ]
```

Sets the specified logging options for the service you are configuring.

The logging options have the following meanings:

Option	Meaning
[NO]ACCEPT	Message is logged when a request is accepted.
[NO]ACTIVATE	Message is logged when the service is activated.
[NO]ADDRESS	For auxiliary server messages and OpenVMS security events, the message displays the IP address as a host name. If host names are not relevant, Compaq recommends that you specify [NO]ADDRESS.
[NO]ALL	Messages are logged for all events.
[NO]CONNECT	Message is logged when the auxiliary server issues a connect request back to the client. The services that usually make this request (on a second socket) are remote shell and remote execute.
[NO]DEACTIVATE	Message is logged when the service is being deactivated.
[NO]ERROR	Message is logged when an error is detected while processing a request to the service.
[NO]EXIT_CLEANUP	Message is logged when the service fails to complete startup (that is, the server did not assign the BG device, with logical name SYS\$NET, or did not issue a C socket before exiting).
[NO]LOGIN	Message is logged when a connected terminal server accepts a remote login request.
[NO]LOGOUT	Message is logged when a connected terminal server terminates a connection.
[NO]MODIFY	Message is logged when the active service is being modified.
[NO]REJECT	Message is logged when a request is rejected.

**/PORT=*n***  
Required.

Port number that the service will use. Specify a number from 1 to 65535.

**/PROCESS\_NAME=*process***  
Required.



Name of the service's process.

Specify a character string up to 15 characters long, truncated to 15 bytes if necessary.

**/PROTOCOL=*protocol* [=options]**

Optional. Default: TCP.

Protocol, and its parameters, that the service will use. To set these parameters, use the following options:

Protocol	Option	Meaning
IP	TYPE_OF_SERVICE= <i>n</i>	Type of service, expressed as a value between 0 and 255.
	TIME_TO_LIVE= <i>n</i>	Maximum number of hops that packets can traverse before being dropped.
TCP (Stream socket type)	[NO]DELAY_ACK	Delays the sending of acknowledgment (ACK) packets. Default: DELAY.
	DROP_COUNT= <i>seconds</i>	TCP connection-request timeout interval for the service.
	PROBE_TIMER= <i>seconds</i>	Maximum number of seconds to probe for idle TCP connections before such a connection times out and closes. Number of seconds between probes for idle connections.
UDP	None	Datagram socket type.

**/REJECT {=[NO]HOSTS=(*hosts* ) |=[NO]NETWORKS=(*networks* ) |=[NO]MESSAGE="*text*" }**

Optional. Default: No rejections if /ACCEPT is set to its default (service all hosts).

- /REJECT=HOST=*host* denies *host* access to the service.
- /REJECT=NOHOST=*host* regrants *host* access to the service.

The following options are available.

Option	Meaning
HOSTS= <i>hosts</i>	Makes the service unavailable to the specified hosts. Maximum is 32. <b>Examples:</b> /REJECT=HOSTS=( <i>host1_name,host2_name, host3_address</i> ) /REJECT=HOSTS=*

## SET SERVICE

Option	Meaning
NOHOSTS= <i>hosts</i>	<p>Removes the specified hosts from the reject list. You can use the wildcard character (*) in place of the <i>hosts</i> list to remove all hosts from the reject list.</p> <p>Maximum is 32.</p> <p><b>Examples:</b></p> <pre>/REJECT=NOHOSTS=(<i>host1_name,host2_name,host3_address</i>)</pre> <pre>/REJECT=NOHOSTS=*</pre>
NETWORKS= <i>networks</i>	<p>Makes the service unavailable to the hosts on the specified networks.</p> <p>Maximum is 16.</p> <p>For each network, you can optionally specify the network mask. The default net mask equals network's class number. For example, for network 11.200.0.0., the default mask is 255.0.0.0.</p> <p><b>Example:</b></p> <pre>/REJECT=NETWORKS=(<i>net1_name,net2_address, net3.net3mask</i>)</pre>
NONETWORKS[= <i>networks</i> ]	<p>Removes the specified networks from the reject list. You can use the wildcard character (*) in place of the <i>networks</i> list to remove all networks from the reject list.</p> <p>Maximum is 16.</p> <p>For each network, you can optionally specify the network mask. The default net mask equals network's class number. For example, for network 11.200.0.0., the default mask is 255.0.0.0.</p> <p><b>Example:</b></p> <pre>/REJECT=NONETWORKS=(<i>net1_name,net2_address, net3.net3mask</i>)</pre>
[NO]MESSAGE= <i>text</i> NOMESSAGE	<p>Message sent to "reject-list" clients when TCP/IP Services rejects their request for the service.</p> <p>Optional.</p> <p>Specify a character string up to 63 characters.</p> <p>Enclose the string in quotation marks.</p> <p>Use this option only for a service whose clients require and support reject messages.</p> <p>Messages are sent with a carriage return/line feed at the end.</p> <p>For RLOGIN, RSH, and REXEC, this message is preceded by a byte with a value of 1 and is terminated with a byte with a value of 0.</p> <p><code>/REJECT=NOMESSAGE</code> deletes the stored message text.</p>

**/RPC=(PROGRAM\_NUMBER=*n*, VERSION\_NUMBER=(LOW=*n*, HIGH=*n*))**  
 Required for services that use the Portmapper; otherwise, not valid. Defaults:

Service	Program Number	Highest Version	Lowest Version
MOUNT	100005	1	1
NFS server	100003	2	2
PCNFS	150001	1	2
PORTMAPPER	100000	1	1

Information that identifies the service to the Portmapper. Use this qualifier for all applications that use RPCs.

**/SEPARATOR=*option=character***  
 Optional. Default: 0 (null).

Character that separates the following fields in received packets:

- PORT=*character*

- USER\_NAME=*character*
- PASSWORD=*character*
- COMMAND=*character*

**/SOCKET\_OPTIONS=(options)**

Optional.

The following socket options are available.

Option	Description	Default
BROADCAST	Sockets are UDP broadcast.	Null character (hexadecimal 00)
NOBROADCAST	Sockets are not UDP broadcast.	
KEEPALIVE	Sockets are TCP keepalive.	Null character (hexadecimal 00)
NOKEEPALIVE	Sockets are not TCP keepalive.	
RECEIVE	Receive socket quota.	Null character (hexadecimal 00)
SEND	Send socket quota.	Null character (hexadecimal 00)

**/USER\_NAME=vms\_user\_account**

Required.

OpenVMS account information for users working on client systems. Required for a user to access the service.

The user must also be defined in the system user authorization file (SYSUAF.DAT).

**Examples**

1. TCPIP> SET SERVICE TOE /USER\_NAME=LITTLE\_PIGGY -  
\_TCPIP /PROCESS\_NAME=TOEd /PORT=1050 /PROTOCOL=UDP -  
\_TCPIP /FILE=SYS\$COMMON:[SYSMGR]TOE\_STARTUP.COM

Defines the service TOE, which implements UDP on port 1050. This service has the OpenVMS process context of user LITTLE\_PIGGY.

After you issue a SET SERVICE TOE command, the auxiliary server executes TOE\_STARTUP.COM when a request arrives for service TOE.

2. TCPIP> SET SERVICE LPD -  
\_TCPIP> /REJECT=NETWORK=(11.30.0.0:255.255.0.0,11.40.0.0)

Sets the LPD service to be inaccessible to the two specified networks.

3. TCPIP> SET SERVICE RSH /FLAGS=(PROXY,CASE\_INSENSITIVE)

Sets the proxy and case-sensitivity flags for the RSH service.

## SHOW ARP

---

## SHOW ARP

Displays ARP information.

**Related command:** SET ARP

### Format

SHOW ARP [*host*] *[/[NO]LOCAL]*

### Parameters

#### *host*

Optional. Default: All hosts; same as specifying /NOLOCAL.

Specifies the host about which you want information.

### Qualifiers

#### **/LOCAL**

#### **[/NO]LOCAL**

Optional. Default: /NOLOCAL.

If you either omit this qualifier or specify /NOLOCAL, the software checks the hosts database. If a lookup fails, it also checks the BIND resolver.

Limits name-to-address lookups to the local hosts database.

### Examples

1. TCPIP> SHOW ARP

Cnt	Flags	Timer	Host	Phys Addr
1:	UC	425	*	00-00-f8-40-ad-91
2:	UC	60	150.110.4.191	08-00-2b-39-4b-40
3:	UC	438	150.110.5.117	00-00-f8-8d-24-d4
4:	UCS	878	150.110.5.109	00-00-f8-4f-f1-63
5:	UCS	426	150.110.5.31	08-00-2b-a1-b1-93
7:	UC	104	150.110.4.2	aa-00-04-00-6d-10

Displays the contents of the ARP table.

The flags have the following meanings:

Flag	Meaning
U	Up, or in use
C	Complete
S	Stale
P	Permanent
D	Dead

2. TCPIP> SHOW ARP PARROT  
parrot (11.170.6.45) at 08-CC-2B-12-C2-BB

Displays IP address-to-hardware address mapping for host PARROT.

---

## SHOW BOOTP

Displays client entries in the BOOTP database.

**Related command:** SET BOOTP

### Format

```
SHOW BOOTP [ host ]
            [ /HARDWARE=ADDRESS=hex_address ]
            [ /LOCAL ]
            [ /OUTPUT=file ]
```

### Parameters

***host***

Optional. Default: Displays all entries.

Host entry you want to display.

### Qualifiers

**/HARDWARE=ADDRESS=*hex\_address***

Optional. Default: None.

Identifies the entry by hardware address.

Specify the address as *hh-hh-hh-hh-hh-hh*.

**/LOCAL**

Optional. Default: The command checks the hosts database; if a lookup fails, it also checks the BIND resolver.

To display hardware-address/IP-identification matches, limits host-name-to-IP-address lookup for each entry in the BOOTP database to the local hosts database.

**/OUTPUT=*file***

Optional. Default: Screen display.

Output is directed to the specified file.

### Examples

```
1.  TCPIP> SHOW BOOTP MYNA /FULL
    Host:          17.22.222.255   myna
                                Hardware Address: 07-06-2B-05-04-03
    Network mask: 255.0.0.0       Type:      Ethernet
    File:          MYNA.SYS
    Time offset:   0               Vendor: Birds, Inc.
    Gateways:     not defined
```

## SHOW BOOTP

```
Servers:  
Cookie:      not defined  
IEN:         not defined  
Impress:     not defined  
Log:         not defined  
LPR:         not defined  
Name:        owl.wise.mouser.edu  
Resource:    not defined  
Time:        not defined  
TCP/IP>
```

**Displays the entry for client `myna` in the BOOTP database. When `myna` requests a download, TCP/IP Services sends system image `MYNA.SYS`.**

---

## SHOW CFS

Displays statistical information about OpenVMS and container file systems.

The NFS server software must be active.

**Related commands:** SHOW NFS

### Format

```
SHOW CFS [ /CONTINUOUS[=n] ]  
          [ /PARAMETERS ]  
          [ /SUMMARY ]
```

### Qualifiers

#### **/CONTINUOUS[=*n*]**

Optional. Default: Static display; /CONTINUOUS=4.

Continuously updates the screen display.

To terminate the display, press Ctrl/Z.

#### **/PARAMETERS**

Optional.

Displays the parameters.

#### **/SUMMARY**

Optional.

Displays the following information:

- Wait states

- Data cache performance

- Summary of allocated services and resources

# SHOW CFS

## Examples

1. TCPIP> SHOW CFS

CFS Services		OpenVMS Services			
CLOSE	14				
CREATE_FH	1	\$ASSIGN	17	\$QIO	0
CREDIR_FH	1	\$DASSGN	15	Access	14
FREEBUFF	0			Create	2
GETATTR	16256	\$DEQ	125	Deaccess	15
LINK_FH	0	\$ENQ	436		
LOOKUP_FH	14			Read_attr	6746
OPEN_FH	14	getVMpage	6	Write_attr	7
READ	8119	freeVMpage	0		
READBUFF	0			Lookup	57
READDIR_FH	13	\$CLREF	26318		
READLINK_FH	0	\$SETEF	26318	Extend	1
REMDIR_FH	1				
REMOVE_FH	2	\$DCLAST	26325	Delete	3
RENAME_FH	2	\$CLRAST	1877	Enter	2
SETATTR	1	\$SETAST	49601	Remove	2
STATFS	1873				
SYMLINK_FH	0	\$GETDVI	1875	Read_V	13
WRITE	5			Write_V	2
OTHER	6	\$CHKPRO	71		
TOTAL	26322				

2. TCPIP> SHOW CFS /SUMMARY

CFS Service status and performance 29-OCT-1998 14:54:36.74

Service State	Cur	Max	Total	Cacheop	Cur	Hit	I/O	Inc	Status
FP-Access	0	0	0	Read	0	0	0	0	Clusize 16
FP-Attributes	0	0	0	Read-A	0	0	0	0	Limit 256
FP-Delete	0	0	0	Write	0	0	0	0	Inuse 0
FP-Dir	0	0	0	Write-A	0	0	0	0	Busy 0
FP-Rename	0	0	0	Write-D	0				Hitrate 0
FP Sub_total	0	0	0						
Buffered	0	0	0	Nameop	Cur	Hit			Status
Internal	0	0	0	-----	----	----			-----
I/O	0	0	0	Add	0				Tabsize 0
Lock	0	0	0	Delete	0				Inuse 0
Logging	0	0	0	Lookup	0	0			Hitrate 0
Resource	0	0	0						
RMS	0	0	0	Fileop	Cur	Hit			Status
Service	0	0	0	-----	----	----			-----
Timer	0	0	0	Find	0	0			Limit 0
Other	0	0	0	Find-A					Inuse 65535
Synch	0	0	0	Find-C		0			Timeout 5
									Hitrate 0
Services count	1	1	3	ATCBs:	1	TBAbS:	0	RDCBs:	1
									Pages: 0

Displays service wait states, data cache performance, and a summary of services and resources.



3. TCPIP> SHOW CFS /PARAMETERS

```
                                CFS PARAMETERS
Data cache
  Size                          256
  Low limit                      4
  High limit                     8
Attribute cache                 Disabled
  Size                           0
  Timeout                        5
Name cache                      Disabled
  Size                           0
Transfer size                   8192
Write size                      512
Output fatal messages to device: _OPA0:
```

**Displays file system information.**

## SHOW COMMUNICATION

---

### SHOW COMMUNICATION

Displays the settings and status for the IP, TCP, UDP, and INET\_ACP software, including routing, buffers, sockets, and memory on the running system.

**Related commands:** SET COMMUNICATION

#### Format

```
SHOW COMMUNICATION [ /MEMORY ]
                   [ /ROUTE ]
                   [ /SECURITY ]
```

#### Qualifiers

##### **/MEMORY**

Optional.

Displays information about memory allocated to data structures associated with network operations.

##### **/ROUTE**

Optional.

Displays routing statistics.

##### **/SECURITY**

Optional.

Displays the security settings specified with the following SET COMMUNICATION qualifiers:

- /ACCEPT
- /REJECT

#### Examples

```
1. TCPIP> SHOW COMMUNICATION/ROUTE
   Route statistics
      Created by redirects           0
      Modified by redirects         0
      Wildcarded lookups            6
      Invalid redirect calls        0
      Failed lookups                0
```

Displays routing statistics.

## SHOW COMMUNICATION

```
2. TCPIP> SHOW COMMUNICATION /MEMORY
1585 mbufs in use:
    490 mbufs allocated to data
    221 mbufs allocated to ancillary data
    2 mbufs allocated to packet headers
    131 mbufs allocated to socket structures
    198 mbufs allocated to protocol control blocks
    180 mbufs allocated to routing table entries
    246 mbufs allocated to socket names and addresses
    21 mbufs allocated to socket options
    76 mbufs allocated to interface addresses
    1 mbufs allocated to kernel table
    2 mbufs allocated to ip multicast options
    7 mbufs allocated to ip multicast address
    10 mbufs allocated to interface multicast address
    1 mbufs allocated to <mbuf type 100>
    1 mbufs allocated to <mbuf type 108>
    3 mbufs allocated to <mbuf type 109>
    7 mbufs allocated to <mbuf type 112>
    28 mbufs allocated to <mbuf type 113>
    28 mbufs allocated to <mbuf type 114>
    3 mbufs allocated to <mbuf type 115>
    3 mbufs allocated to <mbuf type 117>
    5 mbufs allocated to <mbuf type 118>
```

**Displays information about memory usage.**

```
3. TCPIP> SHOW COMMUNICATION /SECURITY
Communication Security Parameters
Allow Log:  Acpt Actv Dactv Conn Error Exit Logi Logo Mdfy Rjct TimO Addr
Force Log:  None
Security device:  disabled
Access lists
  Accept host: 0.0.0.0
  Accept netw: 0.0.0.0
```

**Displays information about security parameters that were specified with the SET COMMUNICATION command.**

## SHOW CONFIGURATION

---

### SHOW CONFIGURATION

Displays the information in the configuration database. This database, read by the TCP/IP Services startup procedure, holds information to:

- Configure the lower-layer protocols, including dynamic routing.
- Configure and enable the Internet interfaces.
- Configure the services you want enabled when TCP/IP Services starts up.
- Configure the BIND resolver.
- Configure the BIND server, including the default domain.
- Configure SMTP.
- Configure SNMP.
- Configure TIME.
- Map file systems.

Because the SET CONFIGURATION commands do not take effect until the next time TCP/IP Services starts up, the SHOW CONFIGURATION command might not display the current settings for the running software. For example, the information you see from SHOW CONFIGURATION PROTOCOL might differ from the SHOW PROTOCOL /PARAMETERS output.

**Related commands:** All SET CONFIGURATION commands

#### Format

```
SHOW CONFIGURATION { component
                     ENABLE SERVICE [service]
                     START ROUTING }
                     [ /COMMON ]
                     [ /FULL ]
                     [ /OUTPUT=file ]
```

#### Parameters

***component***

Required if you do not specify ENABLE SERVICE or START ROUTING.

Component, defined in the configuration database, whose configuration you want to display.

**ENABLE SERVICE [*service*]**

Required if you do not specify *component* or START ROUTING.

Displays either the specified component or all the components that are enabled by the TCP/IP Services startup procedure.

**START ROUTING**

Required if you do not specify *component* or ENABLE SERVICE.

Shows whether or not routing is configured to start running by the TCP/IP Services startup procedure.

## Qualifiers

### **/COMMON**

Optional. Default: Node specific.

Valid only with SHOW CONFIGURATION ENABLE SERVICE.

Displays the information in the configuration database for the clusterwide enabling or disabling of services.

### **/FULL**

Optional. The default is to give a brief listing of the information.

Displays complete information.

Use with the *component* parameter.

### **/OUTPUT=file**

Optional. Default: Screen display.

Writes output to the specified file.

## Examples

1. TCPIP> SHOW CONFIGURATION ENABLE SERVICE

Enable service

FTP, FTP\_CLIENT, LPD, MOUNT, NFS, NFS\_CLIENT, PCNFS,  
PORTMAPPER, REXEC, RSH, SMTP, SNMP

Displays the services configured in the services database that will be enabled by the TCP/IP Services startup procedure.

2. TCPIP> SHOW CONFIGURATION SNMP

SNMP Configuration

Flags: AuthenTraps Sets

Contact: Sam Spade

Location

First: Falcon Building

Second: Los Angeles, California

Community	Type	Address_list
public	Read	0.0.0.0
trapit	Read Trap	136.20.0.10
trapit2	Read Trap	136.20.0.12, 136.20.0.15
rw2	Read Write	136.20.0.15, 136.20.0.100

Displays the SNMP configuration.

## SHOW CONFIGURATION

```
3. TCPIP> SHOW CONFIGURATION NAME_SERVICE
BIND Resolver Configuration

Transport:  UDP
Domain:     fred.parrot.brd.com
Retry:      4
Timeout:    4
Servers:    11.20.208.10, 11.20.208.53
Path:       No values defined
TCPIP>
```

**Displays, from the configuration database, the BIND resolver configuration.**

```
4. TCPIP> SHOW CONFIGURATION INTERFACE

Interface: DE1
IP_Addr:  11.20.208.100    NETWRK: 255.255.0.0  BRDCST: 11.20.255.255

Interface: LO0
IP_Addr:  137.0.0.1       NETWRK: 255.0.0.0   BRDCST:
TCPIP>
```

**Displays the permanent definition of Internet interfaces DE1 and LO0.**

```
5. TCPIP> SHOW CONFIGURATION SMTP

SMTP Configuration

Initial interval:  0 00:30:00.00    Address_max:  16    Options
Retry interval:   0 01:00:00.00    Hop_count_max: 16    NOEIGHT_BIT
Maximum interval: 3 00:00:00.00                                NORELAY
                                                            TOP_HEADERS

Timeout           Initial      Mail      Receipt    Data  Terminate
Send:             5           5         5           3      10
Receive:          5

Alternate gateway: not defined
General gateway:  not defined

Substitute domain: not defined
Zone:             not defined

Postmaster:       TCPIP_SMTP
Log file:         SYS$SPECIFIC:[TCPIP$SMTP]TCPIP$SMTP_LOGFILE.LOG

Generic queue     Queues    Participating nodes
TCPIP$SMTP_CRANE_00  1        CRANE
```

**Displays the SMTP configuration.**

---

## SHOW CONFIGURATION PROTOCOL

Displays information in the configuration database which sets the parameters for ICMP, IP, TCP, and UDP when TCP/IP Services starts up.

**Related commands:** SET CONFIGURATION PROTOCOL, SET PROTOCOL

### Format

```
SHOW CONFIGURATION PROTOCOL [ protocol ]
                             [ /PARAMETERS ]
```

### Parameters

***protocol***

Optional. Default: All protocols.

Specify one of the following: ICMP, IP, TCP, UDP.

### Qualifiers

**/PARAMETERS**

Optional.

Shows parameter settings. You can specify any protocol.

### Examples

1. TCPIP> SHOW CONFIGURATION PROTOCOL

```
ICMP
  Redirect:          enabled
  Unreachable:      disabled

IP
  Forward:          disabled
  Reassembly timer: 0

TCP
  Delay ACK:        enabled
  Window scale:     enabled
  Drop count:       0
  Probe timer:      0
                   Receive          Send
  Push:             disabled         disabled
  Quota:            0                 0

UDP
  Unpriv. broadcast: disabled
                   Receive          Send
  Checksum:         enabled          enabled
  Quota:            0                 0
```

Displays information in the configuration database.

## SHOW DEVICE\_SOCKET

---

### SHOW DEVICE\_SOCKET

Displays:

- Device socket counters
- Current settings from the running communications software

(A device socket is composed of two parts: the internet device (interface) and the socket.)

#### Format

```
SHOW DEVICE_SOCKET [ device_socket ]  
                  [ /CONTINUOUS[=n] ]  
                  [ /FULL ]  
                  [ /HOST=host ]  
                  [ /[NO]LOCAL ]  
                  [ /PORT=n ]  
                  [ /SERVICE=service ]  
                  [ /TYPE=socket_type ]
```

#### Parameters

##### ***device\_socket***

Optional. Default: All device sockets.

Device socket for which you want information.

Specify the characters BG and the device's unit number, for example, BG3, BG17.

#### Qualifiers

##### **/CONTINUOUS[=*n*]**

Optional. Default: Static display; /CONTINUOUS=4.

Automatically updates the display.

Screen update interval in seconds. Valid only for a specific device socket.

To terminate the display, press Ctrl/C.

##### **/FULL**

Optional. The default is to give a brief listing of the information.

Displays complete information, including:

- Application option settings, for example, ACCEPT or FULL\_DUPLEX\_CLOSE
- State of the service
- Counters for receiving and sending buffers

##### **/HOST=*host***

Optional. Default: All hosts.

Displays information for device sockets bound to the specified host.

This does not include device sockets bound to the "ANY host" (address 0.0.0.0).



## SHOW DEVICE\_SOCKET

**/LOCAL**

**/NOLOCAL**

Optional. Default: /LOCAL.

Displays information for device sockets bound to hosts in the local hosts database.

**/NOLOCAL:** Displays information for device sockets bound to hosts in the hosts database and hosts known by the BIND resolver.

**/PORT=*n***

Optional. Default: All local ports.

Displays information for device sockets bound to the specified local port.

**/SERVICE=*service***

Optional. Default: All services.

Displays information for device sockets used for the specified service.

**/TYPE=*socket\_type***

Optional. Default: /TYPE=ALL.

Displays information for the specified type of device socket. Specify one of the following:

- STREAM
- DGRAM

### Examples

1. TCPIP> SHOW DEVICE\_SOCKET BG21 /FULL

```
Device_socket:  BG21          Type: STREAM
                LOCAL
                Port:         21
                Host:         *
                Service:      FTP
                REMOTE
                Port:         0
                Host:         *
                Service:      FTP

                Queued I/O
                QOLEN         0
                QLEN          0
                QLIMIT        1024
                TIMEO         0
                ERROR         0
                OOBMARK       0
                RECEIVE
                SEND
                Socket buffer bytes
                Socket buffer quota
                Total buffer alloc
                Total buffer limit
                Buffer or I/O waits
                Buffer or I/O drops
                I/O completed
                Bytes transferred

                Options:  ACCEPT REUSEADR
                State:    PRIV
                RCV Buff: WAIT
                SND Buff: None
```

Displays complete information about device socket BG21, including the options that are set, for example, the FULL\_DUPLEX\_CLOSE option.

(With the FULL\_DUPLEX\_CLOSE option set, the first data transmission on a TCP connection that has been closed by the remote application returns an EPIPE error. Subsequent send operations on the half-closed socket proceed normally.)

## SHOW DEVICE\_SOCKET

The following table describes the counters in the first column of the display.

Counter	Meaning
Q0LEN	Number of sockets that are about to be connected to the specified socket
QLEN	Number of sockets that have established a connection but have not yet been accepted by the specified socket
QLIMIT	Number of sockets for the Q0LEN and QLEN sockets
TIMEO	Not used
ERROR	Error code temporarily stored on the socket
OOBMARK	Out-of-band mark

2. TCPIP> SHOW DEVICE\_SOCKET BG75 /CONTINUOUS=10

Displays information about device socket BG75 every 10 seconds.

3. TCPIP> SHOW DEVICE\_SOCKET /HOST="lark"

Displays information about all device sockets for remote host lark.

4. TCPIP> SHOW DEVICE\_SOCKET BG1898

Device_socket	Type	Port		Service	Remote
		Local	Remote		Host
bg1898	STREAM	23	2568	TELNET	16.20.176.227

Displays socket type, service, and host information for device BG1898.

---

## SHOW EXPORT

Displays disks/directories available for mounting by NFS clients, in the form of UNIX path names. It also displays the clients allowed to mount these path names.

**Related commands:** ADD EXPORT, REMOVE EXPORT, MAP, SET CONFIGURATION MAP, SET CONFIGURATION NOMAP, SHOW MAP, SHOW CONFIGURATION MAP

### Format

```
SHOW EXPORT [ "/path/name" ]
            [ /HOST=host ]
            [ /OUTPUT=file ]
```

### Restrictions

Requires read access to the export database.

### Parameters

**"/path/name"**

Optional. Default: All exported file systems.

Exported files for which to show access rights.

To specify multiple directory names, separate them with slashes.

### Qualifiers

**/HOST="host\_name"**

Optional. Default: All hosts.

NFS client hosts for which you want to display access rights.

**/OUTPUT=file**

Optional. Default: Screen display. Sends output to the specified file.

### Examples

```
1. TCP/IP> SHOW EXPORT
File system          Host name
/TOUCAN              TOUCAN, toucan
/talkers             parrot
/aviary_dua0        *
/condor_root/root   condor
/condor_root/work4  condor
/nene_d              *
/nfstest_unix/lark1 *
/nfstest_unix/lark2 *
/spoonbill          dove, nuthatch, dove.tree.branch.com
                   toucan, orirole.tree.branch.com
/spoonbill/birdy    dove, DOVE, nuthatch, thrush,
                   thrush.tree.branch.com
/spoonbill/bigbirdy dove
```

Displays exported NFS file systems with the clients that have access rights.

## SHOW EXPORT

2. TCPIP> SHOW EXPORT/HOST="condor"

File System	Host name
/condor_root/root	condor
/condor_root/work4	condor

**Displays exported NFS file systems for clients on host CONDOR.**

---

## SHOW HOST

Displays information from the hosts database.

If the BIND resolver is enabled, information from the BIND database is also displayed.

**Related commands:** SET HOST

### Format

```
SHOW HOST [ host ]  
          [ /ADDRESS=IP_address ]  
          [ /DOMAIN=domain ]  
          [ /LOCAL ]  
          [ /OUTPUT=file ]  
          [ /SERVER=server ]
```

### Restrictions

Requires read access to the hosts database.

### Parameters

#### ***host***

Optional. Default: All hosts.

All alias names for the specified host are displayed.

- If a host has more than one IP address and you specify the name, all its addresses and aliases are displayed.
- If a host has multiple IP addresses and you specify an alias that is defined on multiple IP addresses, only the first IP address and aliases are displayed.
- If you do not specify the *host* parameter or if you use a wildcard, all hosts from the local and BIND databases are displayed.
- If you use a wildcard to complete a host name, no BIND information is displayed.
- If you specify a host, entries are displayed first from the local hosts database, if they exist; otherwise, entries from the BIND database are displayed, if they exist.

### Qualifiers

#### **/ADDRESS=*IP\_address***

Optional. Default: None.

Allows you to select a host by IP address.

- If a host has more than one IP address and you specify the name, all IP addresses and aliases for the host are displayed.
- If a host has multiple IP addresses and you specify an alias that is defined on multiple IP addresses, only the first IP address and aliases are displayed.
- Recommended: Use the *host* parameter instead of this qualifier.

## SHOW HOST

### ***/DOMAIN=domain***

Optional. Default: Name service domain.

Domain to be used by the local host. However, the definition of the domain name is valid only during the execution of the current SHOW HOST command. The BIND request is sent to the specified domain.

### ***/LOCAL***

Optional.

Limits name-to-address lookups to the local hosts database.

### ***/OUTPUT=file***

Optional. Default: Screen display.

Specifies a file for the output of the SHOW HOST command.

### ***/SERVER=server***

Optional. Default: Name server list.

BIND servers to be used. The definition of the server name list is valid only during the execution of the current SHOW HOST command. The request is sent to the specified server.

The list is ordered by request preference. For example, the initial request is sent to the first host in the list. If that host is unavailable, the request is sent to the second host in the list, and so on.

You can specify a maximum of three servers.

## Examples

1. TCPIP> SHOW HOST /LOCAL

```
LOCAL database
Host address  Host name
11.180.6.60   aa80z, AA80Z
11.180.4.1    abbss.zz3.ddd.com, abbss, ABBSS, ab, a
11.180.6.8    alibam, ALIBAM, alb
11.180.5.5    alLpin, ALLPIN, allpine.zz3.ddd.com
11.180.6.30   amfer, AMFER
11.180.6.2    ankles, ANKLES
11.180.6.73   auntie, AUNTIE, maitai
.
.
11.180.4.200  zlepin, ZLEPIN
11.180.20.1   zooley, ZOOLEY, zoo
11.180.6.37   zxtra, ZXTRA
```

The /LOCAL qualifier displays only the hosts in the local database.

```

2. TCPIP> SHOW HOST ABCXYZ
      BIND database
Server:   128.182.4.164   ZSERVE
Host address   Host name
128.180.5.164   ABCXYZ.one.nam.com

```

Displays information about a host found in the BIND database. Note that the display includes the name and address of the BIND server that supplied the information.

```

3. TCPIP> SHOW HOST *

```

Displays the entire hosts database and BIND database (if the resolver is enabled).

In the following examples, host heron has the following IP addresses and aliases:

IP Address	Host	Aliases
100.1	heron	HOST_1A HOST_1B HOST_ALIAS
100.2	heron	HOST_2A HOST_2B HOST_ALIAS

```

4. TCPIP> SHOW HOST HERON

```

Shows all the IP addresses and aliases for the host HERON.

```

5. TCPIP> SHOW HOST HOST_1A

```

Shows IP address 100.1 and the aliases HOST\_1A, HOST\_1B, and HOST\_ALIAS.

```

6. TCPIP> SHOW HOST HOST_ALIAS

```

Shows the host and all aliases for addresses 100.1 and 100.2. Shows all the IP addresses and aliases for host heron.

## SHOW INTERFACE

---

### SHOW INTERFACE

Displays information from the running system for Internet interfaces and pseudointerfaces.

**Related commands:** SHOW CONFIGURATION INTERFACE, SET INTERFACE

#### Format

```
SHOW INTERFACE [ interface ]
                [ /CLUSTER ]
                [ /FULL ]
```

#### Parameters

***interface***

Optional. Default: All interfaces.

Specifies the name of an Internet or pseudo-Internet interface. Examples include ZE0, LO0, QE2, QE3.

#### Qualifiers

**/CLUSTER**

Optional. Default: None.

Displays information about the cluster of which the interface is a member.

**/FULL**

Optional. Default: Brief description is displayed.

Displays full information.

#### Examples

1. TCPIP> SHOW INTERFACE DE0 /FULL

```
Interface: DE0
  IP_Addr: 126.65.100.102  NETWRK: 255.255.255.0  BRDCST: 126.65.100.255
                Ethernet_Addr: AA-00-05-CC-2D-2B  MTU: 65535
  Flags: UP BRDCST RUN
                RECEIVE          SEND
Packets                3817269      595744
  Errors                  0
Collisions:              0
```

Displays information about interface DE0.

The flags that can appear in the display include:

- **AMCST**—The interface will receive multicast packets.
- **BRDCAST**—Indicates the interface supports broadcast messages.
- **DBG**—Driver-level debugging is enabled.
- **LOOP**—The interface is a loopback mode. Packets transmitted on this interface will be looped back in the driver and not be transmitted out on the network.



## SHOW INTERFACE

- **MCAST**—The interface supports multicast packets. However, this does not mean that a multicast address is configured for the interface.
- **NOARP**—The interface is not using address resolution protocol (ARP). It will neither transmit nor respond to ARP requests.
- **PFCPY**—All packets transmitted on this interface are copied and passed to the packet filter program.
- **PTP**— The interface is point-to-point link. This is a read-only flag that is set by the driver.
- **RUN**—Indicates the interface is operational. The driver has allocated resources for the interface and is ready to transmit and receive packets. This option is not applicable to loopback devices, for example, LO0.
- **SMPX**—The interface cannot hear its own transmissions.
- **UP**—Indicates the interface is enabled for use.
- **VMTU**—The interface supports variable maximum transmission unit (MTU) sizes.

## SHOW MAIL

---

## SHOW MAIL

Displays SMTP queue information.

**Related commands:** REMOVE MAIL, SEND MAIL

### Format

```
SHOW MAIL [ user ]
          [ /FULL ]
          [ /RECIPIENT[=options] ]
          [ /ENTRY=n ]
```

### Restrictions

Requires SYSPRV or BYPASS privilege to display information for other users.

### Parameters

**user**

Optional. Default: All users.

Displays SMTP process information of the specified user.

### Qualifiers

**/FULL**

Optional. Default: Brief description is displayed.

Displays detailed information.

**/RECIPIENT[=options]**

Optional. Default: ALL.

Used with /FULL, displays selected recipient classes. Available options include the following:

ALL	Shows failed, sent, and unsent mail messages.
FAILED	Shows messages that could not be read for a particular recipient.
SENT	Shows successful deliveries to a particular recipient.
UNSENT	Shows messages that are as yet unsent.

**/ENTRY=n**

Optional. Default: Your queue entries.

Displays information about the specified queue entry number.

### Examples

1. TCPIP> SHOW MAIL

Displays information about mail messages queued to your process's user name.

2. TCPIP> SHOW MAIL /ENTRY=1234

Displays information about the mail message 1234 in the queue.

## SHOW MAIL

3. TCPIP> SHOW MAIL /FULL /RECIPIENT=ALL

**Displays detailed information about all mail messages sent by the user of your process's user name.**

## SHOW MAP

---

### SHOW MAP

Displays the names of mapped (logically linked) file systems, also called NFS file systems.

**Applies to:** NFS server

**Related commands:** MAP, UNMAP, ADD EXPORT, SHOW EXPORT, REMOVE EXPORT, SET CONFIGURATION MAP, SET CONFIGURATION NOMAP, SHOW CONFIGURATION MAP

#### Format

```
SHOW MAP [ /path/name ]
```

#### Parameters

**/path/name**

Optional.

Name of the file system (the first element of the UNIX file specification).

#### Examples

```
1. TCPIP> SHOW MAP
           Dynamic Filesystem Map
Pathname          Logical File System
/water            USER$DKC100:
/water            USER$DKC100:[WATER]
/duck/pond       USER$DKC100:[DUCK.POND.TEAL]
TCPIP>
```

**Displays all mapped file systems.**

```
2. TCPIP> SHOW MAP "/bird"
           Dynamic Filesystem Map
Pathname          Logical File System
/bird             $1$DUA7:
TCPIP>
```

**Lists mapped file system /bird.**

---

## SHOW MOUNT

Displays a list of mounted directories at all mount points or at a particular mount point.

**Related commands:** MOUNT, DISMOUNT

### Format

```
SHOW MOUNT [ device ]  
            [ /ALL ]  
            [ /FULL ]  
            [ /HOST=host ]
```

### Parameters

#### ***device***

Optional. Default: All mounted file systems.

Local device for which to display mount information. Specify one of the following:

- **DNFS $n$ :** — the full NFS device name and directory tree, for example, DNFS3:[USER.NOTES]
- Volume label
- Logical name for the device

You can use abbreviations and wildcards.

### Qualifiers

#### **/ALL**

Optional.

If you also specify *device*, displays information for all NFS server hosts with mounted file systems on this device.

If you do not specify *device*, displays information for all NFS server hosts with mounted file systems on any device.

Not valid with /HOST.

#### **/FULL**

Optional. Default: Brief description is displayed.

Displays the full, current operating parameters related to each mount.

#### **/HOST=*host***

Optional. Default: All NFS servers with file systems currently mounted.

NFS server on which the physical files reside.

Not valid with /ALL.

## SHOW MOUNT

### Examples

1. TCPIP> SHOW MOUNT  
\_DNFS1:[000000] automount (inactivity timer 0 00:23:00.00), mounted  
SIGMA.PROCESS.COM:/usr  
\_DNFS2:[000000] mounted  
IRIS.PROCESS.COM:/usr/users

**Shows the characteristics of all mounted file systems on all local NFS devices.**

2. TCPIP> SHOW MOUNT DNFS3: /ALL  
\_DNFS3:[A.B] mounted  
SIGMA.PROCESS.COM:/usr  
\_DNFS3:[A.C] mounted  
SIGMA.PROCESS.COM:/work

**Shows the characteristics of all mounted file systems on local device DNFS3:.**

---

## SHOW MX\_RECORD

Displays SMTP routing information. If you omit *destination*, you see the entries in the local Mail Exchange (MX) database. If you specify *destination*, you see all the entries in all the databases that TCP/IP Services would look at, if necessary, to resolve the address.

To send mail, SMTP looks up addresses in one or more databases (if necessary) in the following order:

1. Local MX database
2. Remote MX database
3. BIND server database
4. Local hosts database

**Related command:** SET MX\_RECORD

### Format

```
SHOW MX_RECORD [ destination ]
                [ /GATEWAY=host ]
                [ /OUTPUT=file ]
```

### Parameters

***destination***

Optional. Default: All entries in the local MX database.

Final destination host name.

### Qualifiers

***/GATEWAY=host***

Optional. Default: All destinations.

Displays the destinations that are accessed through the specified gateway.

***/OUTPUT=file***

Optional. Default: Screen display.

Sends the output to the specified file.

### Examples

1. TCP/IP> SHOW MX\_RECORD SWAN
 

		BIND MX database
Server:	18.18.218.10	GREAT.HORNED.OWL.COM
Gate address	Preference	Gate name
18.18.218.10	50	WATER.PIPIT.WEBBED.FEET.COM
18.1.218.16	100	bd-gw.purple.martin.com
188.88.206.2	200	great.horned.owl.com
199.9.214.1	300	bird.food.seeds.worms.com
		BIND database
Server:	18.18.218.10	WATER.PIPIT.WEBBED.FEET.COM

## SHOW MX\_RECORD

Host address	Host name
18.18.100.10	SWAN.WEBBED.FEET.COM

Displays, in order of preference, the routing hops to reach host SWAN if an attempt fails. The local host tries to route through:

1. WATER.PIPIT.WEBBED.FEET.COM
2. bd-gw.purple.martin.com
3. great.horned.owl.com
4. bird.food.seeds.worms.com

Both the alternate gateway and the zone affect how SMTP determines where to relay nonlocal mail.

MX records tell mailers where to relay mail that is destined for a given host. In the display:

- The Gate name field tells where to relay the mail.
- The Gate address field gives the gateway's IP address.
- The Preference field gives each MX record a precedence. A lower preference number means a higher precedence.

2. TCPIP> SHOW MX\_RECORD CROW.COM

```
                                BIND MX database
Server:          18.18.218.10    WATER.PIPIT.WEBBED.FEET.COM
Gate address     Preference     Gate name
159.228.12.253  1                               cawcaw.crow.com
159.228.12.254  2                               scare.crow.com
TCPIP>
```

Displays the MX record for destination host `crow.com`. In the display:

- The Gate name field tells where to relay the mail.
- The Gate address field gives the gateway's IP address.
- The Preference field gives each MX record a precedence. A lower preference number means higher precedence.

In this example, the local host name is WATER, the alternate gateway is `scare.crow.com`, and the zone is `crow.com`. The first preference for delivering mail to `crow.com` is to send to `cawcaw.crow.com`.

If you have not defined an alternate gateway, SMTP tries to relay the mail to `scare.crow` at IP address `158.228.12.253`. It uses the MX records to determine the host to which to relay mail. SMTP tries to relay the mail to each gateway host, in order of preference, until it either successfully transfers the mail or runs out of MX records to try. If there is no alternate gateway, the zone is not used.

If you have defined an alternate gateway, SMTP goes through the list of MX records, but it does not automatically try to relay the mail directly to the gateway. SMTP checks whether the gateway host name is outside or inside the SMTP zone (as defined with SET SMTP CONFIGURATION). If the gateway is inside the SMTP zone, SMTP tries to relay the mail directly to the gateway host. If the gateway is outside the zone, SMTP sends the mail to the alternate gateway.



---

## SHOW NAME\_SERVICE

Logs information about the BIND resolver.

**Related commands:** SET NAME\_SERVICE,  
SHOW CONFIGURATION NAME\_SERVICE

### Format

```
SHOW NAME_SERVICE [ /STATISTICS ]
```

### Qualifiers

#### **/STATISTICS**

Optional.

Dumps statistics to the log file TCPIP\$BIND\_SERVER\_STATISTICS.LOG. In previous versions of the TCP/IP Services product, this qualifier displayed statistical information on the screen.

### Examples

```
1. TCPIP> SHOW NAME_SERVICE
BIND Resolver Parameters
  Local domain: TCPIP.OWL.ROC.COM
  System
    State:      Started, Enabled
    Transport:  UDP
    Domain:     tcpip.owl.roc.com
    Retry:      4
    Timeout:    4
    Servers:    LOCALHOST, tcpip.owl.roc.com
  Process
    State:      Started, Enabled
    Transport:  UDP
    Domain:     11.180.34.3
    Retry:      4
    Timeout:    4
    Servers:    LOCALHOST, lark, crow.moa.awk.com
TCPIP>
```

Shows systemwide and process-specific parameter settings for the BIND resolver.

```
2. TCPIP> SHOW NAME_SERVICE /STATISTICS
```

Logs current BIND server statistics to the file TCPIP\$BIND\_SERVER\_STATISTICS.LOG. The following sample shows such a log file.

## SHOW NAME\_SERVICE

```
+++ Statistics Dump +++ (922292822) Wed Mar 24 11:27:02
34250  time since boot (secs)
15670  time since reset (secs)
12     Unknown query types
20000  A queries
540    SOA queries
2399   MX queries
867    ANY queries
3      AXFR queries

++ Name Server Statistics ++
(Legend)
      RR      RNXD      RFwdR      RDupR      RFail
      RFErr   RErr      RAXFR     RLame     ROpts
      SSysQ   SAns      SFwdQ     SDupQ     SErr
      RQ      RIQ      RFwdQ     RDupQ     RTCP
      SFwdR   SFail    SFErr     SNaAns    SNXD
(Global)
      2 0 0 0 0 0 0 0 0 0 0 2 0 0 0 0 0 0 0 0 0 5 0 0 0 0 0
-- Name Server Statistics --
++ Memory Statistics ++
      3:      9 gets,      2 rem
      4:      7 gets,      0 rem (1 bl, 1022

      5:      16 gets,      1 rem
      6:      7 gets,      5 rem
      7:      10 gets,      5 rem
      8:      97 gets,      16 rem (1 bl, 485 ff)
      13:     6 gets,      4 rem

      .
      .
      .
      664:     5 gets,      1 rem (1 bl, 5 ff)
      732:     2 gets,      0 rem (1 bl, 5 ff)
      1040:    1 gets,      1 rem (1 bl, 2 ff)
>= 1100:    23 gets,      9 rem
-- Memory Statistics --
--- Statistics Dump --- (907337687) Fri Jan 2 10:14:47 1999
```

---

## SHOW NETWORK

Displays information about the networks database.

**Related command:** SET NETWORK

### Format

```
SHOW NETWORK [ network ]
              [ /ADDRESS=address ]
              [ /OUTPUT=file ]
```

### Restrictions

Requires read access to the networks database.

### Parameters

***network***

Optional. Default: All known networks.

Network about which to display information.

- Displays all alias names of the specified network.
- If you specify an alias, the network name and all its alias names are displayed.

### Qualifiers

**/ADDRESS=*address***

Optional. Default: None.

Selects networks by address.

Not valid with the *network* parameter.

**/OUTPUT=*file***

Optional. Default: Screen display.

Output is written to the specified file.

### Examples

```
1. TCPIP> SHOW NETWORK COBNET
   Network address  Network name
   4.0.0.0          COBNET

   Displays the entry for COBNET in the networks database.
```

```
2. TCPIP> SHOW NETWORK Z*
   Network address  Network name
   138.180.4.0      zznet, ZZNET
   120.45.30.0      zzo-net, ZZO-NET, zz01-net
```

From the networks database, displays the entries for all the networks with names or aliases beginning with the letter Z.

## SHOW NFS\_SERVER

---

### SHOW NFS\_SERVER

Displays NFS server performance counters and current parameter settings.

**Related commands:** SET NFS\_SERVER, ZERO NFS\_SERVER

#### Format

```
SHOW NFS_SERVER [ /CONTINUOUS[=seconds] ]  
                [ /RPC ]  
                [ /SERVER=host_name ]  
                [ /VERSION=[V2|V3] ]
```

#### Restrictions

Requires SYSNAM and WORLD privilege.

#### Qualifiers

**/CONTINUOUS[=*seconds*]**

Optional. Defaults: Static display; /CONTINUOUS=4.

Provides a dynamic display, with optional screen-update interval.

To terminate the display, press Ctrl/Z.

**/RPC**

Optional.

Displays statistics for the RPC server.

**/SERVER=*host\_name***

Optional.

Displays information about the host.

**/VERSION=[V2|V3]**

Optional. The default is to show statistics for both versions.

Displays version-specific NFS statistics. You can include either or both arguments.

---

## SHOW PORTMAPPER

Displays a list of all registered remote procedure call (RPC) programs. The Portmapper running on the specified host gets this list.

### Format

```
SHOW PORTMAPPER [ host ]
```

### Parameters

**host**

Optional. Default: Local host.

Host with the Portmapper you want to query.

### Examples

1. TCPIP> SHOW PORTMAPPER

Program	Number	Version	Protocol	Port-number	Process	Service-name
000186A0	( 100000)	2	TCP	111	56E0021D	PORTMAPPER
000186A0	( 100000)	2	UDP	111	56E0021D	PORTMAPPER
000186A3	( 100003)	3	UDP	2049	56E0021F	NFS
000186A5	( 100005)	1	UDP	10	56E00220	MOUNT
000249F1	( 150001)	1	UDP	5151	56E00222	PCNFS

Lists information about all of the currently registered applications.

2. TCPIP> SHOW PORTMAPPER PARROT

Program	Number	Version	Protocol	Port-number	Process	Service-name
000186A0	( 100000)	2	TCP	111	24800126	PORTMAPPER
000186A0	( 100000)	2	UDP	111	24800126	PORTMAPPER

Queries host PARROT for a list of registered applications.

## SHOW PROTOCOL

---

## SHOW PROTOCOL

Displays statistics and configuration information for the specified protocol.

**Related commands:** SET PROTOCOL, ZERO PROTOCOL, SET CONFIGURATION PROTOCOL

### Format

```
SHOW PROTOCOL [ protocol ]  
               [ /PARAMETERS ]
```

### Parameters

*protocol*

Optional. Default: All protocols.

Specify one of the following: ICMP, IP, TCP, UDP.

### Qualifiers

**/PARAMETERS**

Optional.

Shows parameter settings. You can specify any protocol.

### Examples

```
1. TCPIP> SHOW PROTOCOL TCP  
tcp:  
    64213 packets sent  
        56262 data packets (44164814 bytes)  
        49 data packets (39372 bytes) retransmitted  
        7792 ack-only packets (7923 delayed)  
        0 URG only packets  
        0 window probe packets  
        10 window update packets  
        100 control packets  
    50000 packets received  
        37102 acks (for 44165036 bytes)  
        381 duplicate acks  
        0 acks for unsent data  
        23176 packets (194520 bytes) received in-sequence  
        233 completely duplicate packets (290 bytes)  
        50 packets with some dup. data (65 bytes duped)  
        57 out-of-order packets (43 bytes)  
        4 packets (4294967292 bytes) of data after window  
        0 window probes  
        916 window update packets  
        0 packets received after close  
        0 discarded for bad checksums  
        0 discarded for bad header offset fields  
        0 discarded because packet too short  
    54 connection requests  
    35 connection accepts  
    89 connections established (including accepts)  
    91 connections closed (including 3 drops)  
    1 embryonic connection dropped  
    30253 segments updated rtt (of 30286 attempts)  
    14 retransmit timeouts  
        0 connections dropped by rexmit timeout
```

## SHOW PROTOCOL

```
1 persist timeout
2 keepalive timeouts
    2 keepalive probes sent
    0 connections dropped by keepalive
```

Displays the TCP statistics.

The following abbreviations are used for the TCP counters display:

**ack** — acknowledge  
**URG** — urgent  
**dup.** — duplicate  
**embryonic connections**—connections not yet established  
**rtt** — retries  
**rexmt** — retransmit

2. TCPIP> SHOW PROTOCOL TCP /PARAMETERS

```
TCP
Delay ACK:          enabled
Window scale:      enabled
Drop count:        8
Probe timer:       150

                                Receive          Send
Push:              disabled          disabled
Quota:             32768              32768
```

Displays the TCP parameters.

## SHOW PROXY

---

## SHOW PROXY

Displays entries in the proxy database.

**Related commands:** ADD PROXY, REMOVE PROXY

**Applies to:** NFS server, NFS client, PC-NFS, remote shell, LPR/LPD, and customer-developed services

### Format

```
SHOW PROXY [ user_name ]  
            [ /COMMUNICATION ]  
            [ /GID=n ]  
            [ /HOST=host ]  
            [ /NFS =[options] ]  
            [ /UID=n ]
```

### Restrictions

Requires read access to the proxy database.

### Parameters

***user\_name***

Optional. Default: SHOW PROXY \* (all entries).

Specifies the local OpenVMS identity for the user of the NFS server, NFS client, PC-NFS, remote shell, or LPR/LPD.

### Qualifiers

***/COMMUNICATION***

Optional. Default: Displays both communication and NFS proxies.

Displays communication proxies.

***/GID=*n****

Optional. Default: Displays all NFS proxies.

Displays the database entries for all clients with the specified GID.

***/HOST=*host****

Optional. Default: Displays information for all hosts (same as */HOST=\**).

Specifies the remote host from which information is to be displayed.

***/NFS=*option****

Optional. Default:

- If you omit this qualifier, displays both communication and NFS proxies.
- If you omit *option*, displays both incoming and outgoing proxies.

Displays NFS proxies.



## SHOW PROXY

These entries might be for local clients, remote clients, or PC-NFS clients. You can include the following options:

`/NFS=OUTGOING` Proxy to use NFS client  
`/NFS=INCOMING` Proxy to use NFS server  
`/NFS=(OUTGOING,INCOMING)` Proxy to use both the NFS client and the NFS server

`/UID=n`

Optional. Default: All NFS proxies.

Displays the database entry for the client with the specified UID.

### Examples

1. TCPIP> SHOW PROXY /NFS

VMS User_name	Type	User_ID	Group_ID	Host_name
WEBSTER	OD	311	10	*
SHERMAN	ND	115	10	*
COHEN	OND	115	10	*
SILK	ON	115	10	*

Shows the NFS entries in the proxy database:

- WEBSTER has authorization to use the local NFS client (outgoing rights).
- SHERMAN can use the local NFS server (incoming rights).
- COHEN can use both the NFS server and client.
- SILK can use both the NFS server and client. This information is not currently known to NFS because SILK is not loaded in the dynamic database.

In the display, the values in the `Type` field mean:

N	NFS server
O	NFS client
ON	NFS server and client

C	Communication
---	---------------

OD, ND,	Loaded in the NFS cache
OND	

CD	Loaded in the communication cache
----	-----------------------------------

To set up N, O, or ON proxies, see `ADD PROXY /NFS=INCOMING=OUTGOING`.

2. TCPIP> SHOW PROXY /COMMUNICATION

VMS User_name	Type	Remote User_name	Host_name
BLUEJAY	CD	JAY	*
QUETZAL	CD	quetzal	central.america.com
FALCON	CD	FALCON	HAWK
MYNA	C	MYNA	PARROT,parrot
CANVASBACK	CD	CBACK	DUCK,duck

Shows all the communication proxies.

## SHOW ROUTE

---

### SHOW ROUTE

Displays the permanent or volatile routes database. To display the permanent database, use the `/PERMANENT` qualifier.

Looks up the destination you specify first in the hosts database and then, if this lookup fails, in the networks database.

Displays the following routes and their types:

- A — Active route (created manually or associated with an interface)
- D — Dynamic route (created by ROUTED or GATED routing daemon)
- H — Host route (a route to a host)
- N — Network route (a route to a network)
- P — Permanent (from the routes database)

**Related command:** SET ROUTE

#### Format

```
SHOW ROUTE [ destination ]  
            [ /FULL ]  
            [ /GATEWAY=host ]  
            [ /LOCAL ]  
            [ /OUTPUT=file ]  
            [ /PERMANENT ]
```

#### Restrictions

Requires read access to the routes database.

#### Parameters

***destination***

Optional. Default: Displays all routes.

Destination host.

#### Qualifiers

**/FULL**

Optional. Default: Displays routes as specified in the routes database.

Displays mapping between destination addresses and names and gateway addresses and names.

**/GATEWAY=*host***

Optional. Default: All gateways.

Displays information for the specified host that performs as a gateway.

**/LOCAL**

Optional. Default: The command checks the hosts database; if a lookup fails, it checks the BIND resolver.

Limits name-to-address lookups to the local hosts database.

## ***/OUTPUT=file***

Optional. Default: Screen display.

Sends output to the specified file.

## ***/PERMANENT***

Optional.

Displays only the permanent routes database.

- If TCP/IP Services is running and you omit */PERMANENT*, the volatile database is displayed.
- If TCP/IP Services is not running, the permanent database is displayed.

## **Examples**

1. TCP/IP> SHOW ROUTE

```
                                DYNAMIC
Type           Destination           Gateway
AN      0.0.0.0                16.20.0.173
AN      16.20.0.0/16           16.20.208.100
AH      16.20.208.100         16.20.208.100
AH      127.0.0.1              127.0.0.1
```

**Displays all defined routes.**

2. TCP/IP> SHOW ROUTE "robin"

**Displays the network route to host robin.**

## SHOW SERVICE

---

## SHOW SERVICE

Displays the following information about configured services:

- Service name
- Port for listening
- Protocol
- Process name
- IP address
- State
- RPC information

**Related commands:** SET SERVICE, DISABLE SERVICE, ENABLE SERVICE

### Format

```
SHOW SERVICE [ service ]  
              [ /ADDRESS=address ]  
              [ /FULL ]  
              [ /PERMANENT ]  
              [ /PORT=n ]  
              [ /PROCESS=process ]  
              [ /PROTOCOL=protocol ]  
              [ /RPC ]
```

### Parameters

***service***  
Optional. Default: All services.  
Service for which you want information.

### Qualifiers

**/ADDRESS=*address***  
Optional. Default: All services.  
Displays information for only the services that use the specified address.

**/FULL**  
Optional. Default: Brief description is displayed.  
Provides a full display.

**/PERMANENT**  
Optional.  
Defaults:

- If TCP/IP Services is running and you omit the /PERMANENT qualifier, the volatile database is displayed.
- If TCP/IP Services is not running, the permanent database is displayed.

You must include the /PERMANENT qualifier when you specify the /RPC qualifier.

**/PORT=*n***  
Optional. Default: All services.

## SHOW SERVICE

Displays information only for services that use the specified port.

### **/PROCESS=*process***

Optional. Default: All services.

Displays information for only the services that use the specified process.

### **/PROTOCOL=*protocol***

Optional. Default: All services.

Displays information only for services that use the specified protocol.

### **/RPC**

Optional. Default: No RPC information is displayed.

Displays a brief summary of the services that are configured with RPC information. You must include the /PERMANENT qualifier when you specify the /RPC qualifier.

## Examples

1. TCPIP> SHOW SERVICE /RPC /PERMANENT

Service	RPC Program Number	Protocol Versions	
		Lowest	Highest
MOUNT	100005	1	1
NFS	100003	2	2
PCNFS	150001	1	2
PORTMAPPER	100000	2	2

TCPIP>

Displays all previously set RPC information.

2. TCPIP> SHOW SERVICE NFS /FULL /PERMANENT

```
Service: NFS
Port:          2049      Protocol:  UDP      Address:  0.0.0.0
Inactivity:    0         User_name: TCPIP$NFS  Process:  TCPIP$NFS
Limit:         1
File:          TCPIP$SYSTEM:TCPIP$NFS_RUN.COM
Flags:         TCPIP

Socket Opts:  Rcheck Scheck
Receive:      64000     Send:          64000

Log Opts:     Acpt Actv Dactv Conn Error Exit Logi Mdfy Rjct Tim0 Addr
File:        SYS$SYSDEVICE:[TCPIP$NFS]TCPIP$NFS_RUN.LOG

RPC Opts
Program number:  100003  Lowest version:  2  Highest version:  2

Security
Reject msg:  not defined
Accept host: 0.0.0.0
Accept netw: 0.0.0.0
TCPIP>
```

The /FULL and /PERMANENT qualifiers display RPC information for the NFS server, whose program number is 100003, lowest version is 2, and highest version is 2. This information is required for the NFS server to run.

## SHOW SERVICE

3. TCPIP> SHOW SERVICE PCNFS /FULL /PERMANENT

```
Service: PCNFS
Port:          5151 Protocol: TCP,UDP      Address: 0.0.0.0
Inactivity:    0   User_name: TCPIP$PCNFS   Process: TCPIP$PCNFSD
Limit:         1
File:          TCPIP$SYSTEM:TCPIP$PCNFSD_RUN.COM
Flags:         TCPIP Prot
Socket Opts:   Rcheck Scheck
  Receive:     0   Send:                 0
Log Opts:     Acpt Actv Dactv Conn Error Exit Logi Mdfy Rjct TimO Addr
  File:        SYS$SYSDEVICE:[TCPIP$PCNFS]TCPIP$PCNFSD_STARTUP.LOG
RPC Opts
  Program number: 150001  Lowest version: 1   Highest version: 2
Security
  Reject msg: not defined
  Accept host: 0.0.0.0
  Accept netw: 0.0.0.0
```

**Shows the full configuration in the permanent database for PC-NFS. The RPC information shows that PC-NFS runs as program 150001; its lowest version number is 1 and its highest version number is 2.**

4. TCPIP> SHOW SERVICE PORTMAPPER

Service	Port	Protocol	Process	Address	State
PORTMAPPER	111	TCP,UDP	TCPIP\$PORTM	0.0.0.0	Enabled

**Monitors the Portmapper service process, showing that the service is enabled.**

5. TCPIP> SHOW SERVICE LBROKER /FULL /PERMANENT

```
Service: LBROKER
Port:          6570 Protocol: UDP      Address: 0.0.0.0
Inactivity:    0   User_name: TCPIP$LD_BKR   Process: TCPIP$LBROKER
Limit:         1
File:          TCPIP$SYSTEM:TCPIP$LBROKER_RUN.COM
Flags:         None
Socket Opts:   Rcheck Scheck
  Receive:     0   Send:                 0
Log Opts:     Acpt Actv Dactv Conn Error Exit Logi Logo Mdfy Rjct TimO Addr
  File:        SYS$SYSDEVICE:[TCPIP$LD_BKR]TCPIP$LBROKER_RUN.LOG
Security
  Reject msg: not defined
  Accept host: 0.0.0.0
  Accept netw: 0.0.0.0
```

**Displays the settings for cluster load balancing.**

## SHOW SERVICE

```
6. TCPIP> SHOW SERVICE REXEC /FULL /PERMANENT
Service: REXEC
Port:          512 Protocol: TCP           Address: 0.0.0.0
Inactivity:    5  User_name: not defined Process: TCPIP$REXECD
Limit:         3
File:          TCPIP$SYSTEM:TCPIP$REXEC_RUN.COM
Flags:         Case Listen Rexe TCPIP
Socket Opts:   Rcheck Scheck
Receive:       0      Send:           0
Log Opts:      Acpt Actv Dactv Error Exit Mdfy Rjct Tim0 Addr
File:          TCPIP$REXEC.LOG
Separators:
Port: 0      User_name: 0      Password: 0      Command: 0
Security
Reject msg:   not defined
Accept host: 0.0.0.0
Accept netw: 0.0.0.0
```

**Shows the full configuration in the permanent database for REXEC.**

## SHOW VERSION

---

## SHOW VERSION

Displays the version of the TCP/IP Services software that is currently running, including individual components.

### Format

```
SHOW VERSION [ /ALL ]
```

### Qualifiers

**/ALL**

Optional. Default: TCP/IP Services version.

Displays the version of all running TCP/IP Services components.

### Examples

1. TCPIP> SHOW VERSION  
Compaq TCP/IP Services for OpenVMS Alpha Version 5.1  
on an AlphaServer 1000 4/200 running OpenVMS V7.2

Displays the following information:

- Version of TCP/IP Services that is running.
- Model of hardware platform.
- Version of OpenVMS that is running.

2. TCPIP> SHOW VERSION /ALL

```
Compaq TCP/IP Services for OpenVMS Alpha Version V5.1  
on a AlphaServer 4100 5/300 2MB running OpenVMS V7.1
```

Image name	Image ID	Link Date	Image location
Core Environment:			
TCPIP\$ACCESS_SHR;1	TCPIP V5.1	21-DEC-2000	SYS\$COMMON:[SYSLIB]
TCPIP\$BGDRIVER;1	TCPIP V5.1	21-DEC-2000	SYS\$COMMON:[SYS\$LDR]
TCPIP\$GATED;1	TCPIP V5.1	21-DEC-2000	SYS\$COMMON:[SYSEXE]
TCPIP\$INETACP;1	TCPIP V5.1	21-DEC-2000	SYS\$COMMON:[SYSEXE]
TCPIP\$INETDRIVER;1	TCPIP V5.1	21-DEC-2000	SYS\$COMMON:[SYS\$LDR]
TCPIP\$IPC_SHR;1	TCPIP V5.1	21-DEC-2000	SYS\$COMMON:[SYSLIB]
TCPIP\$MESSG;1	TCPIP V5.1	21-DEC-2000	SYS\$COMMON:[SYSMSG]
TCPIP\$PING;1	TCPIP V5.1	21-DEC-2000	SYS\$COMMON:[SYSEXE]
.			
.			
.			
Dynamic Host Configuration Protocol (DHCP):			
TCPIP\$DHCP_BPASCIITODBMOD;1			
	TCPIP V5.1	21-DEC-2000	SYS\$COMMON:[SYSEXE]
TCPIP\$DHCP_BPISAMTOASCII;1	TCPIP V5.1	21-DEC-2000	SYS\$COMMON:[SYSEXE]
TCPIP\$DHCP_BDUMP;1	TCPIP V5.1	21-DEC-2000	SYS\$COMMON:[SYSEXE]
TCPIP\$DHCP_DBMODIFY;1	TCPIP V5.1	21-DEC-2000	SYS\$COMMON:[SYSEXE]
.			
.			
.			

Displays the version of the running TCP/IP Services components and operating system. Also shows the hardware model.



---

## START MAIL

Manually starts the SMTP sender queues (not the receiver [server]).

**Related commands:** SHOW MAIL, ENABLE SERVICE SMTP, SHOW CONFIGURATION SMTP

### Format

START MAIL

### Restrictions

Requires SYSPRV or BYPASS privilege.

SMTP consists of the sender and the receiver. Start the sender before you enable the receiver.

Do not issue this command unless SMTP has been configured (with the SET CONFIGURATION SMTP command).

### Examples

1. TCPIP> START MAIL

Starts the SMTP sender.

(To start the SMTP sender when TCP/IP Services starts up, see the SET CONFIGURATION ENABLE SERVICE command. To start the SMTP receiver, see the ENABLE SERVICE command.)

## START ROUTING

---

## START ROUTING

Starts dynamic routing with ROUTED or GATED. If you want to change from one to the other, you must stop the current dynamic routing daemon then start the desired daemon. You cannot run both GATED and ROUTED at the same time.

**Related commands:** STOP ROUTING, SET GATED

### Format

```
START ROUTING [ /GATED ]  
              [ /LOG ]  
              [ /SUPPLY[=DEFAULT] ]
```

### Qualifiers

#### **/GATED**

Optional.

Enables the gateway routing daemon (GATED).

If you enable dynamic GATED routing, you will be able to configure this host to use any combination of the following routing protocols to exchange dynamic routing information with other hosts on the network:

- RIP (Routing Information Protocol), Versions 1 and 2
- RDISC (Router Discovery Protocol)
- OSPF (Open Shortest Path First)
- EGP (Exterior Gateway Protocol)
- BGP (Border Gateway Protocol), BGP-4
- Static routes

#### **/SUPPLY[=DEFAULT]**

Optional. Applies only to ROUTED. Do not use with /GATED.

Broadcasts routing information to other hosts in 30-second intervals.

If you specify /SUPPLY=DEFAULT, the local host supplies the default network route.

#### **/LOG**

Optional. Applies to ROUTED. Do not use with /GATED.

Logs routing activity to  
SYS\$\$SYSDEVICE:[TCPIP\$ROUTED]TCPIP\$ROUTED.LOG.

Default: No logging.

### Examples

1. TCPIP> START ROUTING /GATED  
Starts GATED dynamic routing on the running system.
2. TCPIP> START ROUTING  
Interactively starts ROUTED dynamic routing on the running system.

## START ROUTING

3. TCPIP> START ROUTING /SUPPLY

**Immediately starts ROUTED dynamic routing. The local host both broadcasts and receives network routing information.**

## STOP ROUTING

---

### STOP ROUTING

Stops dynamic routing. If GATED routing is used, stops dynamic routing but preserves GATED routes in the routing table.

Use with SET NORROUTE when you require full manual control over the routing table.

**Related command:** START ROUTING

#### Format

```
STOP ROUTING [ /GATED ]
```

#### Qualifiers

**/GATED**

Optional.

Use to stop GATED dynamic routing and to remove all GATED routes from the routing table.

---

## UNMAP

Makes unknown to the NFS server either a mapped (logically linked) OpenVMS disk or a container file system.

Unmapping removes a logical file system, also called Network File System (NFS). Unmapped file systems are not accessible to remote users working on NFS clients.

**Related commands:** MAP, SHOW MAP, SET CONFIGURATION NOMAP, ADD EXPORT, SHOW EXPORT, REMOVE EXPORT, MAP, UNMAP, SET CONFIGURATION MAP, SET CONFIGURATION NOMAP, SHOW MAP, SHOW CONFIGURATION MAP

**Applies to:** NFS server

### Format

```
UNMAP "/path/name" [ /([NO]CONFIRM )
```

### Restrictions

Requires SYSPRV and BYPASS privilege.

### Parameters

*"/path/name"*

Required.

UNIX name of the file system to unmap.

You can use wildcards.

### Qualifiers

**/CONFIRM**

**/NOCONFIRM**

Optional. Default: /CONFIRM if you use a wildcard.

Requests confirmation before unmapping each file system.

### Examples

```
1. TCPIP> UNMAP "/disk_host"
```

Unmaps the NFS file system */remote*, making it unavailable to client users.

## ZERO NFS\_SERVER

---

## ZERO NFS\_SERVER

Resets the NFS server performance counters.

**Related commands:** SET NFS\_SERVER, SHOW NFS\_SERVER

### Format

```
ZERO NFS_SERVER [ /HOST=host ]  
                [ /SERVICES ]  
                [ /USER_NAME=vms_user_name ]
```

### Restrictions

Requires SYSNAM and WORLD privileges.

### Qualifiers

#### **/HOST=*host***

Optional. Default: All users, all hosts.

With /USER\_NAME, clears the counters relating to the specified users sharing the specified OpenVMS account.

#### **/SERVICES**

Optional. Default: NFS server services.

Resets the counters for the NFS server and the Mount and Portmapper services.

#### **/USER\_NAME=*vms\_user\_name***

Optional. Default: All users, all hosts.

With /HOST, clears the counters relating to the specified users sharing the specified OpenVMS account.

Do not specify a list of names; specify only a single name.

### Examples

1. TCPIP> ZERO NFS\_SERVER /USER\_NAME=NESTING /HOST="pigeon"

Clears the NFS server counters for the remote NFS clients from host pigeon who use the OpenVMS account NESTING.

## A

---

### Account

#### OpenVMS user

- creating, 2-5, 2-23
- deleting, 2-81
- displaying, 2-186

ADD EXPORT command, 2-2

ADD PROXY command, 2-5

### Address

#### 0.0.0.0

- displaying device sockets, 2-162

#### host-name-to-address lookups

- See* Lookups

#### IP

- defining, 2-98, 2-123
- displaying, 2-170
- mapping IP to Ethernet/FDDI, 2-84, 2-150

### Address Resolution Protocol

- See* ARP

### Alias

- for defining a cluster, 2-99, 2-124

ANALYZE CONTAINER command, 2-8

ANALYZE MAIL command, 2-10

ANALYZE SERVICE command, 2-13

### Anonymous FTP

- See* FTP

### "ANY host"

- displaying device sockets, 2-162

### Applications

#### customer-developed

- ADD PROXY command, 2-5
- registering clients, 2-5

### ARP

SET ARP command, 2-84

SHOW ARP command, 2-150

### Authentication

ADD PROXY command, 2-5, 2-23

CREATE PROXY command, 2-35

REMOVE PROXY command, 2-81

AUTHORIZE command (DCL), 2-5

### Auxiliary server

- messages from, 2-146
- multithreading, 2-145
- restarting the NFS server, 2-135
- uses the BIND resolver, 2-106

### Auxiliary server (cont'd)

- uses the BIND Resolver, 2-131

## B

---

### Berkeley Internet Name Domain

- See* BIND

### BG device driver

- See* Internet interface

### BIND command

- See* MAP command

### BIND database

- SHOW HOST command, 2-167

### Binding

- See* MAP command

### BIND resolver

- configuration
  - displaying, 2-158
- configuring, 2-105, 2-130
- defining the domain, 2-105, 2-130
- deleting the domain, 2-105, 2-130
- disabling, 2-130
- displaying the configuration, 2-179
- enabling, 2-131
- SHOW HOST command, 2-167

### BIND server

- configuration
  - displaying, 2-158
- configuring, 2-105
- CONVERT/CONFIGURATION BIND command, 2-15
- CONVERT/UNIX BIND command, 2-16
- disabling, 2-43
- monitoring, 2-190
- reloading, 2-131
- SET CONFIGURATION BIND command, 2-91

### Booting, remote

- See* BOOTP

### BOOTP

#### Database

- CONVERT/VMS BOOTP command, 2-20
- creating, 2-24
- displaying, 2-151
- disabling, 2-43
- enabling at system startup, 2-97
- monitoring, 2-190
- SET BOOTP command, 2-86

- BOOTP (cont'd)
  - SHOW BOOTP command, 2-151
- BOOTP database
  - adding entries to, 2-86
- Bootstrap Protocol
  - See* BOOTP
- Buffers
  - displaying
    - SHOW COMMUNICATION command, 2-156
  - setting, 2-94

## C

---

- Clients
  - adding, to BOOTP database, 2-86
- Cluster load balancing
  - See* BIND Server
- Commands
  - See* individual commands
- DCL
  - AUTHORIZE, 2-5
  - SHOW DEVICE, 2-37
- displaying information, 1-8
- guidelines for entering, 1-1
- program design
  - configuration commands, 1-4
  - CONVERT commands, 1-5
  - creating database files, 1-5
  - managing NFS, 1-7
  - starting software, 1-6
  - stopping software, 1-6
  - validating databases, 1-6
- UNIX
  - /etc/mount, 2-63
- using, 1-1 to 1-9
  - how to enter, 1-1
- Communication proxies, 2-5
- Communication proxy
  - APPLICATION\_PROXY flag, 2-145
- Configuration
  - BIND Server
    - creating, 2-91
  - creating, 2-25
  - Database
    - BIND Server entries
      - creating, 2-91
    - creating, 2-25
    - displaying, 2-158
    - lower-layer software entries
      - creating, 2-94
    - lower-level protocol entries
      - creating, 2-108
    - Name Server entries
      - creating, 2-105
    - SMTP entries
      - creating, 2-111
    - SNMP entries

- Configuration
  - Database
    - SNMP entries (cont'd)
      - creating, 2-115
  - displaying, 2-158
  - Name Server
    - creating, 2-105
  - permanent
    - See also* individual SET CONFIGURATION commands
  - SMTP
    - creating, 2-111
  - SNMP
    - creating, 2-115
- Configuration protocol
  - displaying, 2-161
- Configuring protocols, 2-137
- Controller
  - Ethernet
    - identifying, 2-98
    - identifying with SET INTERFACE command, 2-124
  - FDDI
    - identifying, 2-98
    - identifying with SET INTERFACE command, 2-124
  - SLIP
    - identifying, 2-98
    - identifying with SET INTERFACE command, 2-124
- CONVERT/CONFIGURATION BIND command, 2-15
- CONVERT/UNIX BIND command, 2-16
- CONVERT/UNIX HOST command, 2-18
- CONVERT/UNIX NETWORK command, 2-19
- CONVERT/VMS BOOTP command, 2-20
- CONVERT/VMS HOST command, 2-21
- CONVERT/VMS NETWORK command, 2-22
- CONVERT/VMS PROXY command, 2-23
- Converting
  - BIND 4 configuration to BIND 8, 2-15
  - CREATE BOOTP command, 2-24
  - CREATE CONFIGURATION command, 2-25
  - CREATE CONTAINER command, 2-26
  - CREATE DIRECTORY command, 2-29
  - CREATE EXPORT command, 2-32
  - CREATE HOST, 2-33
  - CREATE NETWORK, 2-34
  - CREATE PROXY command, 2-35
  - CREATE ROUTE command, 2-36
- Customer-developed applications
  - ADD PROXY command, 2-5
  - registering clients, 2-5



## D

---

### Database

#### BIND

SHOW HOST command, 2-167

#### BIND Server

CONVERT/UNIX BIND command, 2-16

#### BOOTP

adding entries to, 2-86

CONVERT/VMS BOOTP command, 2-20

creating, 2-24

displaying, 2-151

#### Configuration

##### BIND Server entries

creating, 2-91

creating, 2-25

displaying, 2-158

##### lower-layer software entries

creating, 2-94

##### lower-level protocol entries

creating, 2-108

##### Name Server entries

creating, 2-105

##### SMTP entries

creating, 2-111

##### SNMP entries

creating, 2-115

### Export

adding directory names in the Export

Database, 2-2

CREATE EXPORT command, 2-32

deleting directory names from the Export

Database, 2-76

SHOW EXPORT command, 2-165

### Hosts

#### cluster alias

specifying, 2-99, 2-124

CONVERT/UNIX HOST command, 2-18

CONVERT/VMS HOST command, 2-21

SHOW HOST command, 2-167

### MX

SET MX\_RECORD command, 2-128

SHOW MX\_RECORDS command, 2-177

### network

CONVERT/UNIX NETWORK, 2-19

CONVERT/VMS NETWORK, 2-22

### networks

adding entries, 2-133

displaying entries, 2-181

### Proxy

adding entries to, 2-5, 2-23

creating, 2-35

deleting entries from, 2-81

SHOW PROXY command, 2-186

### Routes

CREATE ROUTE command, 2-36

SET MX\_RECORD command, 2-128

### Database

#### Routes (cont'd)

SHOW MX\_RECORDS command, 2-177

#### Services

ANALYZE SERVICE command, 2-13

SET SERVICE command, 2-143

SHOW SERVICE command, 2-190

SHOW MX\_RECORDS command, 2-177

### Data link

*See* Internet interface

### Data link interface

*See* Internet interface

### DCL

AUTHORIZE command, 2-5

SHOW DEVICE command, 2-37

### Defense Data Network

*See* DDN

### DEFINE COMMUNICATION\_CONTROLLER

command, 2-37

### Defining

cluster alias, 2-99, 2-124

interface identifier, 2-99, 2-124

### DELETE COMMUNICATION\_CONTROLLER

command, 2-39

### DELETE CONTAINER command, 2-40

### Device driver

internet, 2-98, 2-123, 2-170

### Device socket

SHOW DEVICE\_SOCKET command, 2-162

### DIRECTORY command, 2-41

### DISABLE SERVICE command, 2-43

### DISCONNECT DEVICE\_SOCKET command, 2-45

### DISMOUNT command, 2-46

### DNFS*n*:

*See* NFS

### DNS

*See also* BIND

### Domain

SET CONFIGURATION BIND command, 2-91

### Domain Name Service

*See* BIND

*See* DNS

### Downline loading

*See* Downloading

### Dynamic routing

*See* Routing

## E

---

### ENABLE SERVICE command, 2-49

### Entering commands

address formats, 1-2

preserving case, 1-3

specifying file and directory names, 1-2

specifying multiple values, 1-2

specifying names and addresses, 1-2

## Entering commands (cont'd)

specifying numeric values, 1-2

## Error logging

*See* Event logging

## ETC.BOOTPTAB file

CONVERT/VMS BOOTP command, 2-20

## /etc/hosts

CONVERT/UNIX HOST command, 2-18

CONVERT/VMS HOST command, 2-21

## /etc/mount command, 2-63

## /etc/networks

CONVERT/UNIX NETWORK, 2-19

CONVERT/VMS NETWORK, 2-22

## Ethernet

### address

mapping to IP, 2-84, 2-150

### controller

identifying, 2-98

identifying with SET INTERFACE

command, 2-124

## Ethernet controller

*See* Network device

## eXchange Identification

*See* XID

## EXIT command, 2-51

## EXPORT command, 2-52

## Export Database

adding directory names in the Export Database,  
2-2

CREATE EXPORT command, 2-32

deleting directory names from the Export  
Database, 2-76

SHOW EXPORT command, 2-165

## F

---

### FDDI

#### address

mapping to IP, 2-84, 2-150

#### controller

identifying, 2-98

identifying with SET INTERFACE

command, 2-124

### FDDI controller

*See* Network device

## Fiber Distributed Data Interface

*See* FDDI

## File identification

*See* FID

## Files-11 On-Disk Structure

*See* ODS-2

## File system

*See* NFS

## File Transfer Protocol

*See* FTP

## FTP

disabling, 2-43

enabling at system startup, 2-97

monitoring, 2-190

## G

---

Gateway Protocol routing, 2-120

## H

---

### Hardware

*See* Network device

### Hardware device

*See* Network device

## HELP command, 2-53

## Host

entry in Hosts Database, 2-121

name-to-address lookups

*See* Lookups

## Host address

defining, 2-98, 2-123

displaying, 2-170

## Hosts Database

### cluster alias

specifying, 2-99, 2-124

CONVERT/UNIX HOST command, 2-18

CONVERT/VMS HOST command, 2-21

SHOW HOST command, 2-167

## I

---

### ICMP

#### ECHO packets

for testing, 2-59, 2-73

#### parameters

setting, 2-108

setting parameters, 2-137

starting, 2-94

## IMPORT command, 2-54

## Interface

*See* Internet interface

## Internet

device driver, 2-98, 2-123, 2-170

## Internet Control Message Protocol

*See* ICMP

## Internet interface

### cluster broadcast mask

defining, 2-99, 2-124

### cluster network mask

defining, 2-99, 2-124

defining, 2-98

defining an IP alias, 2-123

defining broadcast address for, 2-99, 2-124

displaying, 2-170

### new device

defining, 2-37

Internet interface  
  new device (cont'd)  
    deleting, 2-39  
    displaying, 2-57  
  pseudointerface  
    defining, 2-98  
    displaying, 2-170  
  testing  
    SET INTERFACE /LOOPBACK command,  
      2-101, 2-126

Internet Protocol  
  See IP

Interprocess communication  
  See APIs

IP  
  address  
    mapping to Ethernet, 2-84, 2-150  
  parameters  
    setting, 2-108  
  setting parameters, 2-137  
  starting, 2-94

---

## L

LIST COMMUNICATION\_CONTROLLER  
  command, 2-57

Load balancing  
  See BIND Server

Logging  
  See Event logging

Lookups  
  by BIND resolver, 2-131, 2-188  
  in Hosts database, 2-130, 2-150, 2-151, 2-163,  
    2-168, 2-188  
  using BIND Resolver, 2-105  
  using Hosts Database, 2-105

/LOOPBACK qualifier  
  testing internet interfaces, 2-101, 2-126

LOOP command, 2-59

LPD  
  ADD PROXY command, 2-5, 2-23  
  CREATE PROXY command, 2-35  
  disabling, 2-43  
  enabling at system startup, 2-97  
  monitoring, 2-190  
  registering clients, 2-5, 2-23

---

## M

Mail

  See SMTP

Mail exchanger

  See MX Database  
  See SMTP

Mail Exchanger Database

  See MX Database

MAP command, 2-61

Mapping  
  file system to NFS Server  
    See MAP command  
    See NFS  
  name to address  
    See Lookups

Master File Directory  
  See MFD

MFD  
  specifying, 2-68

MOUNT  
  enabling at system startup, 2-97  
MOUNT command, 2-63  
MOUNT command (DCL)  
  similar to SET CONFIGURATION, 2-103

Mounting  
  DISMOUNT command, 2-46  
  displaying mounted file systems  
    SHOW MOUNT command, 2-175  
  mount point  
    specifying, 2-64  
  remote directories  
    MOUNT command, 2-63

Mount point  
  dismounting, 2-46  
  specifying, 2-64, 2-68

MX  
  See MX Database  
  See SMTP

MX Database  
  routing mail  
    SET MX\_RECORD command, 2-128  
    SHOW MX\_RECORD command, 2-177

---

## N

Name service  
  See DNS

Name-to-address lookups  
  See Lookups

Network  
  name-address lookups  
    SET NETWORK command, 2-133  
    SHOW NETWORK command, 2-181

Network management  
  See individual topics  
  remote  
    See SNMP

Network print services  
  See Printing

Networks database  
  adding entries, 2-133  
  CONVERT/UNIX NETWORK, 2-19  
  CONVERT/VMS NETWORK, 2-22  
  displaying entries, 2-181

## NFS

### client

- ADD PROXY command, 2-23
- CREATE PROXY command, 2-35
- DISMOUNT command, 2-46
- MOUNT command, 2-63
- mount point, 2-68
  - dismounting, 2-46
  - specifying, 2-64
- registering clients, 2-23
- SHOW MOUNT command, 2-175

### PC clients

*See* PC-NFS

### server

- CREATE PROXY command, 2-35

## Server

- adding directory names in the Export Database, 2-2
- ADD PROXY command, 2-23
- ANALYZE CONTAINER command, 2-8
- container directory
  - displaying, 2-153
- copying container directory files to OpenVMS files, 2-52
- copying OpenVMS files to container directory files, 2-54
- counters
  - displaying, 2-182
  - resetting, 2-200
- CREATE DIRECTORY command, 2-29
- CREATE EXPORT command, 2-32
- DELETE CONTAINER command, 2-40
- deleting directory names from the Export Database, 2-76
- directories
  - creating, 2-29
- DIRECTORY command, 2-41
- EXPORT command, 2-52
- IMPORT command, 2-54
- links
  - creating, 2-29
  - deleting, 2-75, 2-78
- making files available for mounting, 2-61, 2-103
- making files unavailable, 2-107
- MAP command, 2-61
- mapping
  - SHOW MAP command, 2-174
- mapping file systems
  - SET CONFIGURATION MAP command, 2-103
  - SHOW CONFIGURATION MAP command, 2-158
  - UNMAP command, 2-199
- NFS clients
  - making files unavailable to, 2-199
- parameters
  - displaying, 2-182

## NFS

### Server

- parameters (cont'd)
  - setting, 2-135
- performance
  - monitoring, 2-182
  - resetting counters, 2-200
  - setting parameters, 2-135
- registering clients, 2-23
- REMOVE DIRECTORY command, 2-75
- REMOVE FILE command, 2-78
- REMOVE PROXY command, 2-81
- restarting, 2-135
- SET CONFIGURATION MAP command, 2-103
- SET CONFIGURATION NOMAP command, 2-107
- SET NFS\_SERVER command, 2-135
- SHOW EXPORT command, 2-165
- showing clients, 2-186
- SHOW MAP command, 2-174
- SHOW NFS\_SERVER command, 2-182
- SHOW PROXY command, 2-186
- UNIX file system
  - creating, 2-26
- UNMAP command, 2-199
- unmapping file systems
  - SET CONFIGURATION NOMAP command, 2-107
- unregistering clients, 2-81
- ZERO NFS\_SERVER command, 2-200

### NFS client

- ADD PROXY command, 2-5
- enabling at system startup, 2-97
- registering clients, 2-5

### NFS proxies, 2-5

### NFS server

- ADD PROXY command, 2-5
- enabling at system startup, 2-97
- registering clients, 2-5

## O

### ONC

*See* RPC

### Online help

*See* Help

HELP command, 2-53

### Open Network Computing (ONC)

*See* RPC

### OpenVMS Cluster

- broadcast mask
  - defining, 2-99, 2-124
- /CLUSTER\_TIMER qualifier, 2-88, 2-94
- displaying internet interface information, 2-170
- network mask
  - defining, 2-99, 2-124

## OpenVMS Cluster (cont'd)

SMTP queues, 2-113

## P

### Parameters

#### *container\_file\_system*

DELETE CONTAINER command, 2-40

#### *controller*

DEFINE COMMUNICATION\_  
CONTROLLER command, 2-37

DELETE COMMUNICATION\_  
CONTROLLER command, 2-39

LIST COMMUNICATION\_CONTROLLER  
command, 2-57

#### *destination*

SET MX\_RECORD command, 2-128

SET ROUTE command, 2-140

#### *destination*

SHOW MX\_RECORD command, 2-177

SHOW ROUTE command, 2-188

#### *destination\_file*

CONVERT/UNIX NETWORK command,  
2-19

#### *dest\_file*

CONVERT/UNIX HOST command, 2-18

#### *device*

SHOW MOUNT command, 2-175

#### *device:directory*

CREATE CONTAINER command, 2-26

#### *device:path/name*

ANALYZE CONTAINER command, 2-8

#### *device\_socket*

SHOW DEVICE\_SOCKET command,  
2-162

#### *DNFSn:*

MOUNT command, 2-64

#### ENABLE SERVICE

SHOW CONFIGURATION command,  
2-158

#### *interface*

SET CONFIGURATION INTERFACE  
command, 2-98

SET INTERFACE command, 2-124

SHOW INTERFACE command, 2-170

#### *IP\_address*

SET ARP command, 2-84

#### *logical\_file\_system*

SHOW MAP command, 2-174

#### *logical\_name*

MOUNT command, 2-64

#### *mount\_point*

DISMOUNT command, 2-46

MOUNT command, 2-64

#### *path/name*

UNMAP command, 2-107, 2-199

#### */path/name*

REMOVE DIRECTORY command, 2-75

### Parameters (cont'd)

#### *source\_file*

CONVERT/VMS BOOTP command, 2-20

CONVERT/VMS HOST command, 2-21

CONVERT/VMS NETWORK command,  
2-22

CONVERT/VMS PROXY command, 2-23

#### START ROUTING

SHOW CONFIGURATION command,  
2-158

*user\_name*, 2-186

#### *volume\_label*

MOUNT command, 2-64

#### PATHWORKS IP Driver

*See* PWIP

#### PC-NFS

ADD PROXY command, 2-5, 2-23

CREATE PROXY command, 2-35

disabling, 2-43

enabling system startup, 2-97

monitoring, 2-190

#### Print Server

*See also* Printing

registering clients, 2-5, 2-23

#### PC-NFSd

*See* PC-NFS

#### Performance

*See* Troubleshooting

#### NFS Server

monitoring, 2-182

resetting counters, 2-200

setting parameters, 2-135

#### PING command, 2-73

#### PORTMAPPER

disabling, 2-43

enabling at system startup, 2-97

monitoring, 2-190

SHOW PORTMAPPER command, 2-183

#### Printing

*See also* LPD

*See also* LPR

*See also* PC-NFS

#### LPD

disabling, 2-43

monitoring, 2-190

#### Problem solving

*See* Troubleshooting

#### Protocol

*See also* individual protocols

#### configuring

in Configuration Database, 2-108

#### ICMP

configuring, 2-108

#### IP

configuring, 2-108

#### UDP

configuring, 2-108

Protocols  
  configuring on running system, 2-137

Proxy

  ADD PROXY command, 2-5, 2-23

  CREATE PROXY command, 2-35

  Database

    adding entries to, 2-23

    creating, 2-35

    deleting entries from, 2-81

    SHOW PROXY command, 2-186

  REMOVE PROXY command, 2-81

  SHOW PROXY command, 2-186

Proxy database

  adding entries to, 2-5

Pseudointerface

*See* Internet interface

## Q

### Qualifiers

/ACCEPT, 2-88, 2-94

  SET SERVICE command, 2-144

/ADDRESS, 2-43, 2-49, 2-59, 2-73, 2-115,  
  2-133, 2-145, 2-181

  SET HOST command, 2-121

  SHOW HOST command, 2-167

/ADDRESS\_RETRIES, 2-111

/ADD\_HOST, 2-20

/ADF

  MOUNT command, 2-65

/AFTER, 2-83

/ALIAS

  SET HOST command, 2-121

  SET NETWORK command, 2-133

/ALL, 2-73, 2-194

/ARP

  SET HOST command, 2-99, 2-124

/AUTOMOUNT

  MOUNT command, 2-65

/BACKGROUND

  MOUNT command, 2-66

/BROADCAST, 2-139

/BROADCAST\_MASK

  SET HOST command, 2-99, 2-124

/BYADDRESS, 2-18, 2-19

/CACHE, 2-91

/CACHE\_TIMEOUT

  MOUNT command, 2-66

/CHECK\_INTERFACES

  SET GATED command, 2-120

/CLUSTER, 2-105, 2-130, 2-170

  SET HOST command, 2-99, 2-124

/CLUSTER\_TIMER, 2-88, 2-94

/COMMON, 2-97, 2-159

/COMMUNICATION, 2-81, 2-186

/COMMUNITY, 2-116

/CONFIRM, 2-8, 2-10, 2-13, 2-39, 2-76, 2-79,  
  2-81, 2-83, 2-116, 2-133, 2-141

### Qualifiers (cont'd)

/CONTACT, 2-116

/CONVERT

  IMPORT command, 2-54

  MOUNT command, 2-67

/COPY, 2-79

/C\_BROADCAST\_MASK

  SET HOST command, 2-99, 2-124

/C\_NETWORK

  SET HOST command, 2-99, 2-124

/DATA

  MOUNT command, 2-67

/DEFAULT\_ROUTE, 2-141

/DELAY\_ACK, 2-109, 2-138

/DELETE, 2-10

/DESCRIPTION, 2-37

/DISABLE, 2-130

/DOMAIN, 2-105, 2-130

  CONVERT/UNIX BIND command, 2-16

  SET COMMUNICATION command, 2-88,  
  2-95

  SHOW HOST command, 2-168

/DROP\_COUNT, 2-109, 2-138

/ENABLE, 2-131

/ENTRY, 2-79, 2-83, 2-172

/FILE, 2-20, 2-145

/FILEIDS

  MOUNT command, 2-67

/FLAGS, 2-116, 2-145

/FORCE

  MOUNT command, 2-68

/FORWARD, 2-108, 2-137, 2-139

/FORWARDERS, 2-92

/FULL, 2-59, 2-73, 2-159, 2-162, 2-170,  
  2-172, 2-188

/GATED, 2-119, 2-196, 2-198

/GATEWAY, 2-111, 2-128, 2-141, 2-177, 2-188

/GATEWAYS

  SET BOOTP command, 2-86

/GID, 2-6, 2-82, 2-186

  MOUNT command, 2-68

/GID\_DEFAULT, 2-135

/GROUP

  MOUNT command, 2-68

/HARDWARE, 2-151

  SET BOOTP command, 2-86

/HOLD, 2-11

/HOP\_COUNT\_MAXIMUM, 2-112

/HOST, 2-6, 2-29, 2-68, 2-76, 2-82, 2-162,  
  2-165, 2-175, 2-186, 2-200

  SET HOST command, 2-100, 2-125

/INACTIVITY\_TIMER, 2-135

/INITIALIZE, 2-131

/INTERNET\_INTERFACE, 2-37, 2-39, 2-57

/LIMIT, 2-145

/LOCAL, 2-151, 2-163, 2-188

  SHOW HOST command, 2-168

/LOCAL\_HOST

## Qualifiers

`/LOCAL_HOST` (cont'd)  
    SET COMMUNICATION command, 2-89, 2-95  
`/LOCATION`, 2-116  
`/LOOPBACK`  
    SET HOST command, 2-101, 2-126  
`/MEMORY`  
    SHOW COMMUNICATION command, 2-156  
`/MODE`, 2-29  
    IMPORT command, 2-55  
`/MTU_SEGMENT_SIZE`, 2-109, 2-138  
`/NETWORK`, 2-141  
`/NETWORK_MASK`  
    SET BOOTP command, 2-87  
    SET HOST command, 2-101, 2-126  
`/NFS`, 2-6, 2-82, 2-186  
`/[NO]BROADCAST`, 2-110  
`/[NO]FORWARD`, 2-110  
`/[NO]LOCAL`, 2-150  
`/[NO]PRIMARY`, 2-101  
`/[NO]WINDOW_SCALE`, 2-109, 2-138  
`/NUMBER_PACKETS`, 2-59, 2-73  
`/OPTIONS`, 2-112  
`/OUTPUT`, 2-151, 2-159, 2-165, 2-177, 2-181, 2-189  
`/PACKET_SIZE`, 2-59, 2-73  
`/PARAMETERS`, 2-161, 2-184  
    SHOW CFS command, 2-153  
`/PATH`  
    MOUNT command, 2-68  
`/PATTERN`, 2-60, 2-73  
`/PERMANENT`, 2-82, 2-84, 2-141, 2-189  
`/PORT`, 2-43, 2-49, 2-146, 2-163  
`/PREFERENCE`, 2-128  
`/PRIMARY`, 2-92  
`/PROBE_TIMER`, 2-109, 2-138  
`/PROCESS`, 2-43, 2-49  
`/PROCESSOR`  
    MOUNT command, 2-69  
`/PROCESS_NAME`, 2-146  
`/PROTECTION`  
    MOUNT command, 2-69  
`/PROTOCOL`, 2-43, 2-49  
    SET SERVICE command, 2-147  
`/PROXIES`, 2-89, 2-95  
`/PUBLIC`, 2-84  
`/QUEUES`, 2-113  
`/QUOTA`, 2-109, 2-110, 2-138, 2-139  
`/REASSEMBLY_TIMER`, 2-108, 2-137  
`/RECEIVE_TIMEOUT`, 2-113  
`/RECIPIENT`, 2-172  
`/REDIRECT`, 2-108, 2-137  
`/REJECT`, 2-89, 2-95  
    SET SERVICE command, 2-147  
`/REMOTE_USER`, 2-6, 2-82  
`/REPAIR`, 2-9, 2-11, 2-13

## Qualifiers (cont'd)

`/RETRIES`  
    MOUNT command, 2-69  
`/RETRY`, 2-105, 2-131  
`/ROOT_MODE`, 2-27  
`/ROUTE`, 2-60, 2-74  
    SHOW COMMUNICATION command, 2-156  
`/SAVE_STATE`  
    SET GATED command, 2-120  
`/SECONDARY`, 2-92  
`/SECURITY`  
    SHOW COMMUNICATION command, 2-156  
`/SEND_TIMEOUT`, 2-113  
`/SEPARATOR`, 2-148  
`/SERVER`, 2-106, 2-131  
    SHOW HOST command, 2-168  
`/SERVERS`  
    SET BOOTP command, 2-87  
`/SERVER_TYPE`  
    MOUNT command, 2-69  
`/SERVICE`, 2-163  
`/SERVICES`, 2-200  
`/SHARE`  
    MOUNT command, 2-70  
`/SIZE`, 2-27  
`/SOCKET_OPTIONS`, 2-149  
`/SUBSTITUTE_DOMAIN`, 2-113  
`/SUPERUSER=uid`  
    MOUNT command, 2-70  
`/SUPPLY`  
    START ROUTING command, 2-119, 2-196  
`/SYSTEM`, 2-131  
    MOUNT command, 2-70  
`/THREADS`, 2-136  
`/TIMEOUT`, 2-106, 2-131  
    MOUNT command, 2-70  
`/TIME_OFFSET`  
    SET BOOTP command, 2-87  
`/TOGGLE_TRACE`  
    SET GATED command, 2-120  
`/TRANSPORT`, 2-106, 2-132  
`/TYPE`, 2-37, 2-163  
`/UIC`, 2-26  
`/UID`, 2-7, 2-27, 2-30, 2-82, 2-187  
    IMPORT command, 2-55  
    MOUNT command, 2-70  
`/UID_DEFAULT`, 2-136  
`/UPCASE`, 2-21, 2-22  
`/USER`  
    MOUNT command, 2-71  
`/USER_NAME`, 2-149, 2-200  
    CREATE CONTAINER command, 2-28  
    CREATE DIRECTORY command, 2-30  
`/WAIT`, 2-60, 2-74  
`/WRITE`  
    MOUNT command, 2-71

## Qualifiers (cont'd)

/ZONE, 2-114

## R

---

### Record Management Services

*See* RMS

### Remote booting

*See* BOOTP

### Remote procedure call

*See* RPC

### remote shell

ADD PROXY command, 2-23

CREATE PROXY command, 2-35

registering clients, 2-23

### Remote shell

registering clients, 2-5

REMOVE DIRECTORY command, 2-75

REMOVE EXPORT command, 2-76

REMOVE FILE command, 2-78

REMOVE MAIL command, 2-79

REMOVE PROXY command, 2-81

### Resolver

*See* BIND

### Reverse lookups

*See* Lookups

### Reverse mapping

*See* Lookups

### REXEC

enabling at system startup, 2-97

monitoring, 2-190

### RIP

*See* Routing

### RLOGIN

disabling, 2-43

enabling at system startup, 2-97

monitoring, 2-190

### Route

SET COMMUNICATION command, 2-88

SET CONFIGURATION COMMUNICATION  
command, 2-94

SHOW COMMUNICATION command, 2-156

### Routes Database

CREATE ROUTE command, 2-36

SET MX\_RECORD command, 2-128

SHOW MX\_RECORDS command, 2-177

### Routing

configuring, 2-140

CREATE ROUTE command, 2-36

displaying routes

SHOW ROUTE command, 2-188

dynamic

SET ROUTE command, 2-140

Gateway protocol routing, 2-120

SET MX\_RECORD command, 2-128

SHOW MX\_RECORDS command, 2-177

starting, 2-196

### Routing

starting (cont'd)

upon TCP/IP Services startup, 2-119

static

SET ROUTE command, 2-140

stopping, 2-198

### Routing Information Protocol (RIP)

*See* Routing

### Routing tables

*See* Routing

### RPC

displaying information used by Portmapper,  
2-190

SHOW PORTMAPPER command, 2-183

### RSH

*See* remote shell

disabling, 2-43

enabling at system startup, 2-97

monitoring, 2-190

## S

---

### Security

ADD PROXY command, 2-5, 2-23

CREATE PROXY command, 2-35

REMOVE PROXY command, 2-81

SEND MAIL command, 2-83

### Service

disabling, 2-43

enabling, 2-158

interactively, 2-49

enabling at system startup, 2-97

SET COMMUNICATION command, 2-88

SET CONFIGURATION COMMUNICATION  
command, 2-94

SHOW COMMUNICATION command, 2-156

SHOW CONFIGURATION COMMUNICATION  
command, 2-158

SHOW CONFIGURATION PROTOCOL  
command, 2-161

### Services

#### Database

ANALYZE SERVICE command, 2-13

SET SERVICE command, 2-143

SHOW SERVICE command, 2-190

SET ARP command, 2-84

SET BOOTP command, 2-86

SET COMMUNICATION command, 2-88

SET CONFIGURATION BIND command, 2-91

SET CONFIGURATION COMMUNICATION  
command, 2-94

SET CONFIGURATION ENABLE SERVICE  
command, 2-97

SET CONFIGURATION INTERFACE command,  
2-98



SET CONFIGURATION MAP command, 2-103  
 SET CONFIGURATION NAME\_SERVICE  
   command, 2-105  
 SET CONFIGURATION PROTOCOL command,  
   2-108  
 SET CONFIGURATION SMTP command, 2-111  
 SET CONFIGURATION SNMP command, 2-115  
 SET CONFIGURATION START ROUTING  
   command, 2-119  
 SET GATED command, 2-120  
 SET HOST command, 2-121  
 SET INTERFACE command, 2-123  
 SET MX\_RECORD command, 2-128  
 SET NAME\_SERVICE command, 2-130  
 SET NETWORK command, 2-133  
 SET NFS\_SERVER command, 2-135  
 SET PROTOCOL command, 2-137  
 SET ROUTE command, 2-140  
 SET SERVICE command, 2-143  
 SHOW ARP command, 2-150  
 SHOW BOOTP command, 2-151  
 SHOW CFS command, 2-153  
 SHOW COMMUNICATION command, 2-156  
 SHOW CONFIGURATION command, 2-158  
 SHOW CONFIGURATION PROTOCOL command,  
   2-161  
 SHOW DEVICE  
   DCL command, 2-37  
 SHOW DEVICE\_SOCKET command, 2-162  
 SHOW EXPORT command, 2-165  
 SHOW HOST command, 2-167  
 SHOW INTERFACE command, 2-170  
 SHOW MAIL command, 2-172  
 SHOW MAP command, 2-174  
 SHOW MOUNT command, 2-175  
 SHOW MX\_RECORDS command, 2-177  
 SHOW NAME\_SERVICE command, 2-179  
 SHOW NETWORK command, 2-181  
 SHOW NFS\_SERVER command, 2-182  
 SHOW PORTMAPPER command, 2-183  
 SHOW PROTOCOL command, 2-184  
 SHOW PROXY command, 2-186  
 SHOW ROUTE command, 2-188  
 SHOW SERVICE command, 2-190  
 SHOW VERSION command, 2-194  
 Simple Mail Transfer Protocol  
   *See* SMTP  
 Simple Network Management Protocol  
   *See* SNMP  
 SLIP  
   controller  
     identifying, 2-98  
     identifying with SET INTERFACE  
       command, 2-124  
 SMTP  
   *See also* MX Database  
   ANALYZE MAIL command, 2-10  
   SMTP (cont'd)  
     8-bit characters, 2-112  
     configuration  
       displaying, 2-158  
     disabling, 2-43  
     displaying queue information, 2-172  
     enabling at system startup, 2-97  
     headers, 2-112  
     monitoring, 2-190  
     options  
       8-bit characters, 2-112  
       headers, 2-112  
     queue management, 2-79  
     queues  
       OpenVMS Cluster nodes, 2-113  
     reconfiguring, 2-111  
     REMOVE MAIL command, 2-79  
     requeuing mail, 2-83  
     SEND MAIL command, 2-83  
     SET MX\_RECORD command, 2-128  
     SHOW MX\_RECORDS command, 2-177  
     START MAIL command, 2-195  
   SNMP  
     configuration  
       creating, 2-115  
       displaying, 2-158  
     disabling, 2-43  
     enabling at system startup, 2-97  
     monitoring, 2-190  
   Specifying  
     address formats, 1-2  
     file and directory names, 1-2  
     multiple values in commands, 1-2  
     names and addresses, 1-2  
     numeric values, 1-2  
   Stanford Research Institute  
     *See* APIs  
   START MAIL command, 2-195  
   START ROUTING command, 2-196  
   Static routing  
     *See* Routing  
   STOP ROUTING command, 2-198  
   Subnetworking  
     *See* Routing  
   Subnetwork routing  
     *See* Routing  
   Sun ONC RPC  
     *See* RPC  
   Sun RPC  
     *See* RPC

## T

---

### TCP

- parameters
  - setting, 2-108
- setting parameters, 2-137
- starting, 2-94

### TELNET

- disabling, 2-43
- enabling at system startup, 2-97
- monitoring, 2-190

#### Print Symbiont

*See* Printing

### TELNETSYM

*See also* Printing

### Terminal emulation

- of IBM 3270 model terminals
  - See* TELNET

### Testing

- for active connectivity
  - LOOP command, 2-59
  - PING command, 2-73
- internet interface
  - SET INTERFACE /LOOPBACK command, 2-101, 2-126

### TFTP

- disabling, 2-43
- enabling at system startup, 2-97
- monitoring, 2-190

### TIME

- configuration
  - displaying, 2-158

### TN3270

*See* TELNET

### Transmission Control Protocol/Internet Protocol

*See* TCP/IP

### Trivial File Transfer Protocol

*See* TFTP

### Troubleshooting

- internet controller
  - DELETE COMMUNICATION\_ CONTROLLER command, 2-39
- NFS Server
  - ANALYZE CONTAINER command, 2-8
- Services Database
  - ANALYZE SERVICE command, 2-13
- SMTP
  - ANALYZE MAIL command, 2-10

## U

---

### UDP

- parameters
  - setting, 2-108
- setting parameters, 2-137
- starting, 2-94

### UIC

- container directories
  - copying into with IMPORT command, 2-56
- specifying with CREATE CONTAINER command, 2-26
- specifying with CREATE DIRECTORY command, 2-30

### UNIX

/etc/mount command, 2-63

UNIX file system

- creating, 2-26

### UNIX commands

using, 1-8

### UNIX-style files

*See* NFS

### UNMAP command, 2-199

### User Datagram Protocol

*See* UDP

### User Identification Code

*See* UIC

### User services

*See* End-user services

## V

---

### Version

- of software
  - displaying, 2-194

## Y

---

### Yellow Pages

- format
  - CONVERT/UNIX HOST command, 2-18

## Z

---

ZERO NFS\_SERVER command, 2-200